

GlassFish Server Open Source Edition

High Availability Administration Guide Release 4.0

May 2013

This book describes thehigh-availability features in GlassFish Server, including converged load balancing, HTTP load balancing, clusters, session persistence and failover.

Note: The main thrust of the GlassFish Server Open Source Edition 4.0 release is to provide an application server for developers to explore and begin exploiting the new and updated technologies in the Java EE 7 platform. Thus, the clustering, standalone instance and high availability features of GlassFish Server were not a focus of this release. These features are included in the release, but they may not function properly with some of the new features added in support of the Java EE 7 platform.

Copyright © 2013, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Pr	reface	x
1	High Availability in GlassFish Server	
	Overview of High Availability	1-1
	Load Balancing With the Apache mod_jk or mod_proxy_ajp Module	
	High Availability Session Persistence	
	High Availability Java Message Service	
	RMI-IIOP Load Balancing and Failover	1-2
	How GlassFish Server Provides High Availability	
	Storage for Session State Data	1-3
	Highly Available Clusters	1-3
	Recovering from Failures	
	Recovering the Domain Administration Server	1-5
	Recovering GlassFish Server Instances	1-5
	Recovering the HTTP Load Balancer and Web Server	1-5
	Recovering Message Queue	1-6
	More Information	1-7
2	Enabling Centralized Administration of GlassFish Server Instances	
	About Centralized Administration of GlassFish Server Instances	
	Determining Whether to Enable Centralized Administration	
	Considerations for Using DCOM for Centralized Administration	
	Considerations for Using SSH for Centralized Administration	
	Setting Up DCOM and Testing the DCOM Set Up	
	Windows Operating System Settings	
	To Enable the Windows User to Run Scripts on a Remote Host	
	To Set Up Password Authentication for the Windows User	
	To Test the Connection Over DCOM to a Remote Host	
	Setting Up Cygwin SSH on Windows	
	To Download and Install Cygwin	
	To Set the Path for Windows and for the Cygwin Shell	
	To Set the Home Directory for the Cygwin SSH User	
	To Configure and Start the Cygwin SSH Server Daemon sshd	
	Setting Up the MKS Toolkit on Windows	
	To Install the MKS Toolkit	2-11

	To Set the Path for Windows and for the MKS Toolkit Shell	2-12
	To Set the Home Directory for the MKS Toolkit SSH User	2-12
	To Configure and Start the MKS Toolkit SSH Server Daemon sshd	2-14
	Setting Up SSH on UNIX and Linux Systems	2-14
	To Set Up SSH on Oracle Solaris Systems	2-15
	To Set Up SSH on MacOS Systems	2-15
	To Set Up SSH on Linux systems	2-16
	Testing the SSH Setup on a Host	2-16
	To Test the SSH Setup on a Host	2-17
	Setting Up SSH User Authentication	2-17
	To Set Up Public Key Authentication Without Encryption	2-18
	To Set Up Encrypted Public Key Authentication	2-20
	To Set Up Password Authentication	2-23
	Installing and Removing GlassFish Server Software on Multiple Hosts	2-24
	To Copy a GlassFish Server Installation to Multiple Hosts	2-25
	To Remove GlassFish Server Software From Multiple Hosts	2-27
3	Administering GlassFish Server Nodes	
	Types of GlassFish Server Nodes	
	Creating, Listing, Testing, and Deleting DCOM Nodes	
	To Create a DCOM Node	
	To List DCOM Nodes in a Domain	
	To Test if a DCOM Node is Reachable	
	To Delete a DCOM Node	
	Creating, Listing, Testing, and Deleting SSH Nodes	3-6
	To Create an SSH Node	3-6
	To List SSH Nodes in a Domain	
	To Test if an SSH Node is Reachable	3-8
	To Delete an SSH Node	3-9
	Creating, Listing, and Deleting CONFIG Nodes	3-10
	To Create a CONFIG Node	3-10
	To List CONFIG Nodes in a Domain	
	To Delete a CONFIG Node	3-12
	Updating and Changing the Type of a Node	3-13
	To Update a DCOM Node	3-13
	To Update an SSH Node	3-14
	To Update a CONFIG Node	3-15
	To Change the Type of a Node	3-16
4	Administering GlassFish Server Clusters	
•	About GlassFish Server Clusters	/1_1
	Group Management Service	
	Protocols and Transports for GMS	
	GMS Configuration Settings	
	Dotted Names for GMS Settings	
	To Preconfigure Nondefault GMS Configuration Settings	
	To Change GMS Settings After Cluster Creation	
	10 Divinge Sino Settings Finer Crawler Creation	¬ C

	To Check the Health of Instances in a Cluster	. 4-7
	To Validate That Multicast Transport Is Available for a Cluster	. 4-7
	Discovering a Cluster When Multicast Transport Is Unavailable	. 4-9
	Using the Multi-Homing Feature With GMS	4-13
	Creating, Listing, and Deleting Clusters	4-15
	To Create a Cluster	4-15
	To List All Clusters in a Domain	4-18
	To Delete a Cluster	4-19
5	Administering GlassFish Server Instances	
	Types of GlassFish Server Instances	
	Administering GlassFish Server Instances Centrally	
	To Create an Instance Centrally	
	To List All Instances in a Domain	
	To Delete an Instance Centrally	
	To Start a Cluster	
	To Stop a Cluster	
	To Start an Individual Instance Centrally	
	To Stop an Individual Instance Centrally	
	To Restart an Individual Instance Centrally	
	Administering GlassFish Server Instances Locally	
	To Create an Instance Locally	
	To Delete an Instance Locally	
	To Start an Individual Instance Locally	
	To Stop an Individual Instance Locally	
	To Restart an Individual Instance Locally	
	Resynchronizing GlassFish Server Instances and the DAS	
	Default Synchronization for Files and Directories	
	To Resynchronize an Instance and the DAS Online	
	To Resynchronize Library Files.	
	To Resynchronize Custom Configuration Files for an Instance	
	To Resynchronize Users' Changes to Files	5-26
	To Resynchronize Additional Configuration Files	5-26
	To Prevent Deletion of Application-Generated Files	
	To Resynchronize an Instance and the DAS Offline	5-27
	Migrating EJB Timers	5-29
	To Enable Automatic EJB Timer Migration for Failed Clustered Instances	5-29
	To Migrate EJB Timers Manually	5-30
6	Administering Named Configurations	
	About Named Configurations	. 6-1
	Types of Named Configurations	. 6-1
	The default-config Configuration	
	Automatically Created Configurations	
	Directory for Configuration Synchronization	. 6-2
	Creating, Listing, and Deleting Named Configurations	. 6-2

	To Create a Named Configuration	6-3
	To List the Named Configurations in a Domain	6-4
	To List the Targets of a Named Configuration	6-4
	To Delete a Named Configuration	6-5
	Modifying Properties for Named Configurations and Instances	
	Properties for Port Numbers in a Named Configuration	6-7
	To Modify a Named Configuration's Properties	
	To Modify Port Numbers of an Instance	
7	Configuring HTTP Load Balancing	
	Setting Up HTTP Load Balancing	7-1
	Prerequisites for Setting Up HTTP Load Balancing	
	Configuring GlassFish Server with Apache HTTP Server and mod_jk	
	Configuring GlassFish Server with Apache HTTP Server and mod_proxy_ajp	
	HTTP Load Balancer Deployments	
8	Upgrading Applications Without Loss of Availability	
	Application Compatibility	8-1
	Upgrading In a Single Cluster	
	To Upgrade an Application in a Single Cluster	
	Upgrading in Multiple Clusters	
	To Upgrade a Compatible Application in Two or More Clusters	
	Upgrading Incompatible Applications	
	To Upgrade an Incompatible Application by Creating a Second Cluster	
_		
9	Configuring High Availability Session Persistence and Failover	0.4
	Overview of Session Persistence and Failover	
	Requirements	
	Restrictions	
	Scope	
	Enabling the High Availability Session Persistence Service	
	To Enable Availability for a Cluster, Standalone Instance or Container	
	Configuring Availability for Individual Web Applications	
	Configuring Replication and Multi-Threaded Concurrent Access to HttpSessions	
	Using Single Sign-on with Session Failover	
	Using Coherence*Web for HTTP Session Persistence	
	Stateful Session Bean Failover	
	Configuring Availability for the EJB Container	
	Configuring Availability for an Individual Application or EJB Module	
	Configuring Availability for an Individual Bean	
	Specifying Methods to Be Checkpointed	9-9
10	Configuring Java Message Service High Availability	
	Using Message Queue Broker Clusters With GlassFish Server	10-1
	About Message Queue Broker Clusters	10-1
	Configuring GlassFish Clusters to Use Message Queue Broker Clusters	10-2

	To Configure a GlassFish Cluster to Use an Embedded or Local Conventional Broker Clus With Master Broker 10-3	ter
	To Configure a GlassFish Cluster to Use an Embedded or Local Conventional Broker Clus of Peer Brokers 10-4	ter
	To Change the Master Broker in an Embedded or Local Broker Cluster	10-5
	To Migrate Between Types of Embedded or Local Conventional Broker Clusters	10-5
	To Configure a GlassFish Cluster to Use a Local Enhanced Broker Cluster	10-5
	To Configure a GlassFish Cluster to Use a Remote Broker Cluster	10-6
	Connection Failover	10-7
		100
	Load-Balanced Delivery to MDBs	10-8
11	RMI-IIOP Load Balancing and Failover	11-1
11	RMI-IIOP Load Balancing and Failover Overview	
11	RMI-IIOP Load Balancing and Failover	11-1
11	RMI-IIOP Load Balancing and Failover Overview General Requirements for Configuring Load Balancing	11-1 11-1
11	RMI-IIOP Load Balancing and Failover Overview	11-1 11-1 11-1
11	RMI-IIOP Load Balancing and Failover Overview	11-1 11-1 11-1 11-2
11	RMI-IIOP Load Balancing and Failover Overview	11-1 11-1 11-1 11-2 11-2
11	RMI-IIOP Load Balancing and Failover Overview	11-1 11-1 11-1 11-2 11-2
11	RMI-IIOP Load Balancing and Failover Overview	11-1 11-1 11-2 11-2 11-2 11-3

List of Examples

2–1	Creating an Alias for the Windows User's Password	2-7
2–2	Testing the Connection Over DCOM to a Remote Host	2-8
2–3	Setting the Home Directory for the MKS Toolkit User	2-13
2–4	Determining if the sshd Daemon Is Running on an Oracle Solaris System	2-15
2–5	Determining if the sshd Daemon Is Running on a Linux System	2-16
2–6	Setting Up Public Key Authentication Without Encryption	2-19
2–7	Setting Up Encrypted Public Key Authentication	2-22
2–8	Creating an Alias for the SSH User's Password	2-24
2–9	Copying a GlassFish Server Installation to Multiple DCOM-Enabled Hosts	
2-10	Copying a GlassFish Server Installation to Multiple SSH-Enabled Hosts	
2–11	Removing GlassFish Server Software From Multiple DCO\M-Enabled Hosts	
2–12	Removing GlassFish Server Software From Multiple SSH-Enabled Hosts	
3–1	Creating a DCOM Node	
3–2	Listing Basic Information About All DCOM Nodes in a Domain	
3–3	Listing Detailed Information About All DCOM Nodes in a Domain	
3–4	Testing if a DCOM Node Is Reachable	
3–5	Deleting a DCOM Node	
3–6	Creating an SSH Node	
3–7	Listing Basic Information About All SSH Nodes in a Domain	
3–8	Listing Detailed Information About All SSH Nodes in a Domain	
3–9	Testing if an SSH Node Is Reachable	
3–10	Deleting an SSH Node	
3–11	Creating a CONFIG Node	
3–12	Listing Basic Information About All CONFIG Nodes in a Domain	
3–13	Listing Detailed Information About All CONFIG Nodes in a Domain	
3–14	Deleting a CONFIG Node	
3–15	Updating a DCOM Node	
3–16	Updating an SSH Node	
3–17	Updating a CONFIG Node	
3–18	Changing a CONFIG Node to an SSH Node	
4–1	Checking the Health of Instances in a Cluster	
4–2	Validating That Multicast Transport Is Available for a Cluster	
4–3	Discovering a Cluster When Multiple Instances are Running on a Host	
4–4	Discovering a Cluster by Specifying a List of IP Addresses	
4–5	Discovering a Cluster by Generating a List of Locations of Instances	
4–6	Creating a Cluster for a Network in Which Multicast Transport Is Available	
4–7	Creating a Cluster and Setting GMS Options for a Network in Which Multicast Trans	
	Is Available 4-17	port
4–8	Listing All Clusters in a Domain	4-18
4–9	Listing All Clusters That Are Associated With a Node	
4–10	Deleting a Cluster	
5–1	Creating a Clustered Instance Centrally	
5–2	Listing Basic Information About All GlassFish Server Instances in a Domain	
5–3	Listing Detailed Information About All GlassFish Server Instances in a Domain	
5–4	Deleting an Instance Centrally	
5–5	Starting a Cluster	
5–6	Stopping a Cluster	
5–7	Starting an Individual Instance Centrally	
5–8	Stopping an Individual Instance Centrally	
5–9	Restarting an Individual Instance Centrally	
5–10	Creating a Clustered Instance Locally Without Specifying a Node	5-14
5–10	Creating a Clustered Instance Locally Without Specifying a Node	
5–12	Deleting an Instance Locally	
5–12	Starting an Individual Instance Locally	
	CONTAIN ALL LIGHT I WART I DOUTICE DOCULT I	

5–14	Stopping an Individual Instance Locally	5-18
5–15	Restarting an Individual Instance Locally	5-19
5–16	Resynchronizing an Instance and the DAS Online	5-23
5–17	Updating the Option for Locating a Configuration File	5-25
5–18	config-files File	5-27
5–19	Resynchronizing an Instance and the DAS Offline	5-29
5–20	Migrating an EJB Timer	5-31
6–1	Creating a Named Configuration	6-3
6–2	Listing All Named Configurations in a Domain	6-4
6–3	Listing the Targets of a Named Configuration	6-5
6–4	Deleting a Named Configuration	6-6
6–5	Modifying a Property of a Named Configuration	6-9
6–6	Modifying a Port Number for an Instance	6-10
7–1	httpd.conf File for Load Balancing	7-3
7–2	workers.properties File for Load Balancing	7-3
9–1	Example of an EJB Deployment Descriptor With Availability Enabled	9-9
9–2	Example of EJB Deployment Descriptor Specifying Methods Checkpointing	9-10
11–1	Setting Load-Balancing Weights for RMI-IIOP Weighted Round-Robin Load Balancing 11-5	ζ

List of Tables

Preface

This book describes the high-availability features in GlassFish Server, including converged load balancing, HTTP load balancing, clusters, session persistence and failover.

Note: The main thrust of the GlassFish Server Open Source Edition 4.0 release is to provide an application server for developers to explore and begin exploiting the new and updated technologies in the Java EE 7 platform. Thus, the clustering, standalone instance and high availability features of GlassFish Server were not a focus of this release. These features are included in the release, but they may not function properly with some of the new features added in support of the Java EE 7 platform.

This preface contains information about and conventions for the entire GlassFish Server Open Source Edition (GlassFish Server) documentation set.

GlassFish Server 4.0 is developed through the GlassFish project open-source community at http://glassfish.java.net/. The GlassFish project provides a structured process for developing the GlassFish Server platform that makes the new features of the Java EE platform available faster, while maintaining the most important feature of Java EE: compatibility. It enables Java developers to access the GlassFish Server source code and to contribute to the development of the GlassFish Server. The GlassFish project is designed to encourage communication between Oracle engineers and the community.

Oracle GlassFish Server Documentation Set

The GlassFish Server documentation set describes deployment planning and system installation. For an introduction to GlassFish Server, refer to the books in the order in which they are listed in the following table.

Book Title	Description	
Release Notes	Provides late-breaking information about the software and the documentation and includes a comprehensive, table-based summary of the supported hardware, operating system, Java Development Kit (JDK), and database drivers.	
Quick Start Guide	Explains how to get started with the GlassFish Server product.	
Installation Guide	Explains how to install the software and its components.	

Tials Cameran
Fish Server. product
ssFish enterprise.
Fish Server y using the from the ration
g GlassFish
he oyment
Enterprise ed to run open Java ion ormation
ish Server is
higher alancing.
h Server.
r when n.
nen using
· GlassFish nd related
ng bugs for
rchitecture, ging
messaging
essage ng Message ement
or that work

Book Title	Description
Message Queue Developer's Guide for C Clients	Provides programming and reference information for developers working with Message Queue who want to use the C language binding to the Message Queue messaging service to send, receive, and process Message Queue messages.

Typographic Conventions

The following table describes the typographic changes that are used in this book.

Typeface	Meaning	Example
AaBbCc123	The names of commands, files,	Edit your .login file.
	and directories, and onscreen computer output	Use 1s a to list all files.
	The state of the s	machine_name% you have mail.
AaBbCc123	What you type, contrasted with	machine_name% su
	onscreen computer output	Password:
AaBbCc123	A placeholder to be replaced with a real name or value	The command to remove a file is rm <i>filename</i> .
AaBbCc123	Book titles, new terms, and terms	Read Chapter 6 in the <i>User's Guide</i> .
	to be emphasized (note that some emphasized items appear bold	A <i>cache</i> is a copy that is stored locally.
	online)	Do <i>not</i> save the file.

Symbol Conventions

The following table explains symbols that might be used in this book.

Symbol	Description	Example	Meaning
[]	Contains optional arguments and command options.	ls [-1]	The -1 option is not required.
{ }	Contains a set of choices for a required command option.	-d {y n}	The -d option requires that you use either the y argument or the n argument.
\${ }	Indicates a variable reference.	\${com.sun.javaRoot}	References the value of the com.sun.javaRoot variable.
_	Joins simultaneous multiple keystrokes.	Control-A	Press the Control key while you press the A key.
+	Joins consecutive multiple keystrokes.	Ctrl+A+N	Press the Control key, release it, and then press the subsequent keys.
>	Indicates menu item selection in a graphical user interface.	File > New > Templates	From the File menu, choose New. From the New submenu, choose Templates.

Default Paths and File Names

The following table describes the default paths and file names that are used in this book.

Placeholder	Description	Default Value	
as-install	Represents the base installation directory for GlassFish Server.	Installations on the Oracle Solaris operating system, Linux operating system, and Mac OS operating system:	
	In configuration files, <i>as-install</i> is represented as follows:	user's-home-directory/glassfish3/glassfish	
		Installations on the Windows operating system:	
	<pre>\${com.sun.aas.installRoot}</pre>	SystemDrive:\glassfish3\glassfish	
as-install-parent	Represents the parent of the base installation directory for GlassFish	Installations on the Oracle Solaris operating system, Linux operating system, and Mac operating system:	
	Server.	user's-home-directory/glassfish3	
		Installations on the Windows operating system:	
		SystemDrive:\glassfish3	
domain-root-dir	Represents the directory in which a domain is created by default.	as-install/domains/	
domain-dir	Represents the directory in which a domain's configuration is stored.	domain-root-dir/domain-name	
	In configuration files, <i>domain-dir</i> is represented as follows:		
	<pre>\${com.sun.aas.instanceRoot}</pre>		
instance-dir	Represents the directory for a server instance.	domain-dir/instance-name	

Documentation, Support, and Training

The Oracle web site provides information about the following additional resources:

- Documentation (http://docs.oracle.com/)
- Support (http://www.oracle.com/us/support/index.html)
- Training (http://education.oracle.com/)

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

High Availability in GlassFish Server

This chapter describes the high availability features in GlassFish Server Open Source Edition 4.0.

The following topics are addressed here:

- Overview of High Availability
- How GlassFish Server Provides High Availability
- Recovering from Failures
- More Information

Overview of High Availability

High availability applications and services provide their functionality continuously, regardless of hardware and software failures. To make such reliability possible, GlassFish Server provides mechanisms for maintaining application state data between clustered GlassFish Server instances. Application state data, such as HTTP session data, stateful EJB sessions, and dynamic cache information, is replicated in real time across server instances. If any one server instance goes down, the session state is available to the next failover server, resulting in minimum application downtime and enhanced transactional security.

GlassFish Server provides the following high availability features:

- Load Balancing With the Apache mod_jk or mod_proxy_ajp Module
- High Availability Session Persistence
- High Availability Java Message Service
- RMI-IIOP Load Balancing and Failover

Load Balancing With the Apache mod_jk or mod_proxy_ajp Module

A common load balancing configuration for GlassFish Server 4.0 is to use the Apache HTTP Server as the web server front-end, and the Apache mod_jk or mod_proxy_ajp module as the connector between the web server and GlassFish Server. See Configuring GlassFish Server with Apache HTTP Server and mod_jk and Configuring GlassFish Server with Apache HTTP Server and mod_proxy_ajp for more information.

High Availability Session Persistence

GlassFish Server provides high availability of HTTP requests and session data (both HTTP session data and stateful session bean data).

Java EE applications typically have significant amounts of session state data. A web shopping cart is the classic example of a session state. Also, an application can cache frequently-needed data in the session object. In fact, almost all applications with significant user interactions need to maintain session state. Both HTTP sessions and stateful session beans (SFSBs) have session state data.

Preserving session state across server failures can be important to end users. If the GlassFish Server instance hosting the user session experiences a failure, the session state can be recovered, and the session can continue without loss of information. High availability is implemented in GlassFish Server by means of in-memory session replication on GlassFish Server instances running in a cluster.

For more information about in-memory session replication in GlassFish Server, see How GlassFish Server Provides High Availability. For detailed instructions on configuring high availability session persistence, see Configuring High Availability Session Persistence and Failover.

High Availability Java Message Service

GlassFish Server supports the Java Message Service (JMS) API and JMS messaging through its built-in jmsra resource adapter communicating with Open Message Queue as the JMS provider. This combination is often called the JMS Service.

The JMS service makes JMS messaging highly available as follows:

Message Queue Broker Clusters

By default, when a GlassFish cluster is created, the JMS service automatically configures a Message Queue broker cluster to provide JMS messaging services, with one clustered broker assigned to each cluster instance. This automatically created broker cluster is configurable to take advantage of the two types of broker clusters, conventional and enhanced, supported by Message Queue.

Additionally, Message Queue broker clusters created and managed using Message Queue itself can be used as external, or remote, JMS hosts. Using external broker clusters provides additional deployment options, such as deploying Message Queue brokers on different hosts from the GlassFish instances they service, or deploying different numbers of Message Queue brokers and GlassFish instances.

For more information about Message Queue clustering, see Using Message Queue Broker Clusters With GlassFish Server.

Connection Failover

The use of Message Queue broker clusters allows connection failover in the event of a broker failure. If the primary JMS host (Message Queue broker) in use by a GlassFish instance fails, connections to the failed JMS host will automatically fail over to another host in the JMS host list, allowing messaging operations to continue and maintaining JMS messaging semantics.

For more information about JMS connection failover, see Connection Failover.

RMI-IIOP Load Balancing and Failover

With RMI-IIOP load balancing, IIOP client requests are distributed to different server instances or name servers, which spreads the load evenly across the cluster, providing scalability. IIOP load balancing combined with EJB clustering and availability also provides EJB failover.

When a client performs a JNDI lookup for an object, the Naming Service essentially binds the request to a particular server instance. From then on, all lookup requests

made from that client are sent to the same server instance, and thus all EJBHome objects will be hosted on the same target server. Any bean references obtained henceforth are also created on the same target host. This effectively provides load balancing, since all clients randomize the list of target servers when performing JNDI lookups. If the target server instance goes down, the lookup or EJB method invocation will failover to another server instance.

IIOP Load balancing and failover happens transparently. No special steps are needed during application deployment. If the GlassFish Server instance on which the application client is deployed participates in a cluster, the GlassFish Server finds all currently active IIOP endpoints in the cluster automatically. However, a client should have at least two endpoints specified for bootstrapping purposes, in case one of the endpoints has failed.

For more information on RMI-IIOP load balancing and failover, see RMI-IIOP Load Balancing and Failover.

How GlassFish Server Provides High Availability

GlassFish Server provides high availability through the following subcomponents and features:

- Storage for Session State Data
- Highly Available Clusters

Storage for Session State Data

Storing session state data enables the session state to be recovered after the failover of a server instance in a cluster. Recovering the session state enables the session to continue without loss of information. GlassFish Server supports in-memory session replication on other servers in the cluster for maintaining HTTP session and stateful session bean data.

In-memory session replication is implemented in GlassFish Server 4.0 as an OSGi module. Internally, the replication module uses a consistent hash algorithm to pick a replica server instance within a cluster of instances. This allows the replication module to easily locate the replica or replicated data when a container needs to retrieve the data.

The use of in-memory replication requires the Group Management Service (GMS) to be enabled. For more information about GMS, see Group Management Service.

If server instances in a cluster are located on different hosts, ensure that the following prerequisites are met:

- To ensure that GMS and in-memory replication function correctly, the hosts must be on the same subnet.
- To ensure that in-memory replication functions correctly, the system clocks on all hosts in the cluster must be synchronized as closely as possible.

Highly Available Clusters

A highly available cluster integrates a state replication service with clusters and load balancer.

Note: When implementing a highly available cluster, use a load balancer that includes session-based stickiness as part of its load-balancing algorithm. Otherwise, session data can be misdirected or lost. An example of a load balancer that includes session-based stickiness is the Loadbalancer Plug-In available in Oracle GlassFish Server.

Clusters, Instances, Sessions, and Load Balancing

Clusters, server instances, load balancers, and sessions are related as follows:

- A server instance is not required to be part of a cluster. However, an instance that is not part of a cluster cannot take advantage of high availability through transfer of session state from one instance to other instances.
- The server instances within a cluster can be hosted on one or multiple hosts. You can group server instances across different hosts into a cluster.
- A particular load balancer can forward requests to server instances on multiple clusters. You can use this ability of the load balancer to perform an online upgrade without loss of service. For more information, see Upgrading in Multiple Clusters.
- A single cluster can receive requests from multiple load balancers. If a cluster is served by more than one load balancer, you must configure the cluster in exactly the same way on each load balancer.
- Each session is tied to a particular cluster. Therefore, although you can deploy an application on multiple clusters, session failover will occur only within a single cluster.

The cluster thus acts as a safe boundary for session failover for the server instances within the cluster. You can use the load balancer and upgrade components within the GlassFish Server without loss of service.

Protocols for Centralized Cluster Administration

GlassFish Server uses the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to ensure that clusters that span multiple hosts can be administered centrally. To perform administrative operations on GlassFish Server instances that are remote from the domain administration server (DAS), the DAS must be able to communicate with those instances. If an instance is running, the DAS connects to the running instance directly. For example, when you deploy an application to an instance, the DAS connects to the instance and deploys the application to the instance.

However, the DAS cannot connect to an instance to perform operations on an instance that is not running, such as creating or starting the instance. For these operations, the DAS uses DCOM or SSH to contact a remote host and administer instances there. DCOM or SSH provides confidentiality and security for data that is exchanged between the DAS and remote hosts.

Note: The use of DCOM or SSH to enable centralized administration of remote instances is optional. If the use of DCOM SSH is not feasible in your environment, you can administer remote instances locally.

For more information, see Enabling Centralized Administration of GlassFish Server Instances.

Recovering from Failures

You can use various techniques to manually recover individual subcomponents after hardware failures such as disk crashes.

The following topics are addressed here:

- Recovering the Domain Administration Server
- Recovering GlassFish Server Instances
- Recovering the HTTP Load Balancer and Web Server
- Recovering Message Queue

Recovering the Domain Administration Server

Loss of the Domain Administration Server (DAS) affects only administration. GlassFish Server clusters and standalone instances, and the applications deployed to them, continue to run as before, even if the DAS is not reachable

Use any of the following methods to recover the DAS:

- Back up the domain periodically, so you have periodic snapshots. After a hardware failure, re-create the DAS on a new host, as described in "Re-Creating the Domain Administration Server (DAS)" in GlassFish Server Open Source Edition Administration Guide.
- Put the domain installation and configuration on a shared and robust file system (NFS for example). If the primary DAS host fails, a second host is brought up with the same IP address and will take over with manual intervention or user supplied automation.
- Zip the GlassFish Server installation and domain root directory. Restore it on the new host, assigning it the same network identity.

Recovering GlassFish Server Instances

GlassFish Server provide tools for backing up and restoring GlassFish Server instances. For more information, see To Resynchronize an Instance and the DAS Offline.

Recovering the HTTP Load Balancer and Web Server

There are no explicit commands to back up only a web server configuration. Simply zip the web server installation directory. After failure, unzip the saved backup on a new host with the same network identity. If the new host has a different IP address, update the DNS server or the routers.

Note: This assumes that the web server is either reinstalled or restored from an image first.

The Load Balancer Plug-In (plugins directory) and configurations are in the web server installation directory, typically /opt/SUNWwbsvr. The web-install/web-instance/config directory contains the loadbalancer.xml file.

Recovering Message Queue

When a Message Queue broker becomes unavailable, the method you use to restore the broker to operation depends on the nature of the failure that caused the broker to become unavailable:

- Power failure or failure other than disk storage
- Failure of disk storage

Additionally, the urgency of restoring an unavailable broker to operation depends on the type of the broker:

- Standalone Broker. When a standalone broker becomes unavailable, both service availability and data availability are interrupted. Restore the broker to operation as soon as possible to restore availability.
- **Broker in a Conventional Cluster.** When a broker in a conventional cluster becomes unavailable, service availability continues to be provided by the other brokers in the cluster. However, data availability of the persistent data stored by the unavailable broker is interrupted. Restore the broker to operation to restore availability of its persistent data.
- Broker in an Enhanced Cluster. When a broker in an enhanced cluster becomes unavailable, service availability and data availability continue to be provided by the other brokers in the cluster. Restore the broker to operation to return the cluster to its previous capacity.

Recovering From Power Failure and Failures Other Than Disk Storage

When a host is affected by a power failure or failure of a non-disk component such as memory, processor or network card, restore Message Queue brokers on the affected host by starting the brokers after the failure has been remedied.

To start brokers serving as Embedded or Local JMS hosts, start the GlassFish instances the brokers are servicing. To start brokers serving as Remote JMS hosts, use the imqbrokerd Message Queue utility.

Recovering from Failure of Disk Storage

Message Queue uses disk storage for software, configuration files and persistent data stores. In a default GlassFish installation, all three of these are generally stored on the same disk: the Message Queue software in as-install-parent/mq, and broker configuration files and persistent data stores (except for the persistent data stores of enhanced clusters, which are housed in highly available databases) in domain-dir/imq. If this disk fails, restoring brokers to operation is impossible unless you have previously created a backup of these items. To create such a backup, use a utility such as zip, gzip or tar to create archives of these directories and all their content. When creating the backup, you should first quiesce all brokers and physical destinations, as described in "Quiescing a Broker" and "Pausing and Resuming a Physical Destination" in Open Message Queue Administration Guide, respectively. Then, after the failed disk is replaced and put into service, expand the backup archive into the same location.

Restoring the Persistent Data Store From Backup. For many messaging applications, restoring a persistent data store from backup does not produce the desired results because the backed up store does not represent the content of the store when the disk failure occurred. In some applications, the persistent data changes rapidly enough to make backups obsolete as soon as they are created. To avoid issues in restoring a persistent data store, consider using a RAID or SAN data storage solution that is fault tolerant, especially for data stores in production environments.

More Information

For information about planning a high-availability deployment, including assessing hardware requirements, planning network configuration, and selecting a topology, see the GlassFish Server Open Source Edition Deployment Planning Guide. This manual also provides a high-level introduction to concepts such as:

- GlassFish Server components such as node agents, domains, and clusters
- IIOP load balancing in a cluster
- Message queue failover

For more information about developing applications that take advantage of high availability features, see the GlassFish Server Open Source Edition Application Development Guide.

For information on how to configure and tune applications and GlassFish Server for best performance with high availability, see the GlassFish Server Open Source Edition Performance Tuning Guide, which discusses topics such as:

- Tuning persistence frequency and persistence scope
- Checkpointing stateful session beans
- Configuring the JDBC connection pool
- Session size
- Configuring load balancers for best performance

More	nform	ation
IVIOTE	ınınrm	ation

Enabling Centralized Administration of GlassFish Server Instances

GlassFish Server uses the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to ensure that clusters that span multiple hosts can be administered centrally. To perform administrative operations on GlassFish Server instances that are remote from the domain administration server (DAS), the DAS must be able to communicate with those instances. If an instance is running, the DAS connects to the running instance directly. For example, when you deploy an application to an instance, the DAS connects to the instance and deploys the application to the instance.

However, the DAS cannot connect to an instance to perform operations on an instance that is not running, such as creating or starting the instance. For these operations, the DAS uses DCOM or SSH to contact a remote host and administer instances there. DCOM or SSH provides confidentiality and security for data that is exchanged between the DAS and remote hosts.

Note: The use of DCOM or SSH to enable centralized administration of remote instances is optional. If the use of DCOM or SSH is not feasible in your environment, you can administer remote instances locally.

The following topics are addressed here:

- About Centralized Administration of GlassFish Server Instances
- Setting Up DCOM and Testing the DCOM Set Up
- Setting Up Cygwin SSH on Windows
- Setting Up the MKS Toolkit on Windows
- Setting Up SSH on UNIX and Linux Systems
- Testing the SSH Setup on a Host
- Setting Up SSH User Authentication
- Installing and Removing GlassFish Server Software on Multiple Hosts

About Centralized Administration of GlassFish Server Instances

The use of DCOM or SSH to enable centralized administration of remote instances is optional and is required only for specific operations. Instances local to the DAS can be administered without DCOM or SSH. If DCOM or SSH is not practicable in your environment, you can administer remote instances locally.

Determining Whether to Enable Centralized Administration

Before setting up a GlassFish Server cluster, use the following considerations to determine whether to enable centralized administration of remote instances:

- If you are planning a large cluster of many instances, consider enabling centralized administration of instances in the cluster. Centralized administration of instances simplifies the administration of the cluster by enabling you to perform all administrative operations on the cluster and its instances from the DAS.
- If you are planning a small cluster of few instances, consider whether enabling centralized administration requires more effort than logging in to individual hosts to administer remote instances locally.

How you administer instances and the nodes on which they resides varies depending on whether and how centralized administration is enabled. The following table provides cross-references to instructions for administering nodes and instances depending on the protocol that is used for enabling centralized administration, if any.

Protocol	Node Administration Instructions	Instance Administration Instructions	
DCOM	Creating, Listing, Testing, and Deleting DCOM Nodes	Administering GlassFish Server Instances Centrally	
SSH	Creating, Listing, Testing, and Deleting SSH Nodes	Administering GlassFish Server Instances Centrally	
None	Creating, Listing, and Deleting CONFIG Nodes	Administering GlassFish Server Instances Locally	

Considerations for Using DCOM for Centralized Administration

DCOM enables communications between Windows hosts. In a typical GlassFish Server deployment, the DAS acts as a DCOM client, and hosts where instances reside act as DCOM servers. To create or start an instance on a remote host, the DAS instructs the DCOM server on the host to start the asadmin utility of GlassFish Server. The asadmin utility then performs the required operation on the host to create or start the instance.

The DCOM service must be running on hosts where instances reside, but is not required to be running on the DAS host. The DAS uses its own DCOM client for communicating with hosts where instances reside. On Windows hosts, the DCOM server is typically running by default as a Windows Service.

DCOM is available only with the Windows operating system. Because DCOM is typically installed and preconfigured, minimal additional setup is required to use DCOM with GlassFish Server.

Before setting up DCOM, decide which Windows user GlassFish Server will use when connecting to remote hosts. For the following reasons, administration is simplest if the Windows user is the user that starts the DAS:

- Remote instances are started as the Windows user.
- By default, the DAS assumes that the Windows user is the user that is running the DAS.

Considerations for Using SSH for Centralized Administration

In a typical GlassFish Server deployment, the DAS acts as the SSH client, and hosts where instances reside act as SSH servers. The SSH Server Daemon sshd must be running on hosts where instances reside, but is not required to be running on the DAS host. The DAS uses its own SSH client for communicating with hosts where instances reside. However, to generate keys and test SSH setup, a native SSH client must be installed on the DAS host.

The requirements for SSH configuration and user management are different for each operating system on which GlassFish Server is supported. Therefore, the use of SSH for centralized administration involves using SSH tools to configure SSH on the operating system that you are using.

On UNIX and Linux systems, SSH is typically installed and preconfigured, and requires minimal additional setup. On Windows systems, additional setup is required to install and configure an SSH provider.

Obtaining SSH Software

On UNIX and Linux systems, SSH software is typically installed as part of the base operating system.

However, on Windows systems, you must install one of the following SSH providers:

- Cygwin (http://www.cygwin.com/) release 1.7.6
- MKS Toolkit for Developers (http://www.mkssoftware.com) release 9.2

Determining the SSH User

Before setting up SSH, decide which SSH user GlassFish Server will use when connecting to remote hosts. For the following reasons, administration is simplest if the SSH user is the user that starts the DAS:

- For public key authentication, the user that starts the DAS must be able to read the SSH user's private key file.
- Remote instances are started as the SSH user.
- By default, the DAS assumes that the SSH user is the user that is running the DAS.

Requirements for the SSH User's Environment

The environment of the SSH user on any remote host to which the user will connect must meet the requirements that are stated in "Paths and Environment Settings for the JDK Software" in GlassFish Server Open Source Edition Release Notes.

The SSH user's environment on a host is set by the environment set-up files that are run when the user uses SSH to run a command on the host. You must ensure that these files set up the SSH user's environment correctly.

The files that are run when the user uses SSH to run a command are different than the files that are run when the user logs in to a host. For example, in the bash shell, .profile and .bashrc are run when the user logs in, but only .bashrc is run when the user runs a command. Therefore, in the bash shell, you must ensure that .bashrc contains the required environment settings for the SSH user.

File Access Permissions on UAC-Enabled Windows Systems

Note: The User Account Control (UAC)

(http://technet.microsoft.com/en-us/library/cc7096 91%28WS.10%29.aspx) feature is available only on some versions of the Windows operating system, for example, Windows 7, Windows Vista, and Windows 2008.

You might be using a UAC-enabled Windows system and choose to store files for GlassFish Server instances in a directory other than the SSH user's home directory. In this situation, the SSH user must have native (that is, nonvirtual) read and write access to the file system where the instances are to be stored. The OS-level administrator has such access by default. You can also configure the system to grant such access to other users. For more information, see the documentation for the Windows operating system.

Setting Up DCOM and Testing the DCOM Set Up

Setting up DCOM on a host involves the following tasks:

- Verifying Windows operating system settings for the host
- Enabling the Windows user to run scripts on the host
- Setting up password authentication for the Windows user on the host

Set up DCOM on all hosts where instances in your cluster will reside.

After setting up DCOM on a host, test the connection over DCOM to the host.

Windows Operating System Settings

To enable access to a host over DCOM, ensure that the following items in the Windows operating system are set as follows on the host:

- The following services are in the started state and are set to start automatically:
 - Server
 - Remote Registry
- Network Access: Sharing security model for local accounts is set to Classic.
- The following ports are open:
 - DCOM port 135 or 139
 - Windows Shares port 445

To Enable the Windows User to Run Scripts on a Remote Host

To run scripts on a remote host, full control over the following Windows registry keys must be allowed for the Windows user or the group that contains the Windows user:

- One of the following keys, depending on the processor architecture of the host:
 - 32-bit architecture: HKEY_LOCAl_ MACHINE\SOFTWARE\Classes\Wow6432Node\CLSID\\76A64158-CB41-1 1D1-8B02-00600806D9B6}

- 64-bit architecture: HKEY_LOCAl_ MACHINE\SOFTWARE\Classes\CLSID\\76A64158-CB41-11D1-8B02-006008 06D9B6}
- HKEY LOCAL MACHINE\SOFTWARE\Classes\CLSID\\{72C24DD5-D70A-438B-8A42-98424B88 AFB8

In some versions of Windows, only the user NT SERVICE\TrustedInstaller has full control over these Windows registry keys. If your version of Windows is configured in this way, you must modify these keys to allow full control over them for the Windows user or the group that contains the Windows user.

Note: Only the operating-system-level administrator user can edit the Windows registry.

Perform this procedure for each Windows registry key that you are modifying on each host where instances in your cluster will reside.

1. If necessary, start the Registry Editor.

regedit.exe

The Registry Editor window opens.

- 2. In the Registry Editor window, navigate to the registry key that you are modifying.
- **3.** Select the key, click mouse button 3, and from the pop-up menu that opens, select Permissions.

The Permissions window for the key opens.

- 4. Determine whether full control is allowed for the Windows user or the group that contains the Windows user.
 - If full control is allowed, no further action is required.
 - If full control is not allowed, allow full control as follows:
 - In the Permissions window, click Advanced.

The Advanced Security Settings window for the key opens.

- **b.** In the Advanced Security Settings window, select the Owner tab.
- **c.** From the Change owner to list, select the Windows user or the group that contains the Windows user.
- **d.** Ensure that the Replace owner on subcontainer and objects option is selected.
- **e.** Click Apply, then OK.

The Advanced Security Settings window closes. The Permissions window shows that full control is allowed for the Windows user or the group that contains the Windows user.

f. In the Permissions window, click OK.

The Permissions window closes.

After modifying all the Windows registry keys over which full control is required, quit the Registry Editor.

Next Steps

Set up password authentication for the Windows user as explained in To Set Up Password Authentication for the Windows User.

To Set Up Password Authentication for the Windows User

When a GlassFish Server subcommand uses DCOM to log in to a remote host, GlassFish Server requires the Windows user's password to authenticate the Windows user. To provide this password securely to GlassFish Server, create a GlassFish Server password alias to represent the password and store this alias in a password file that is passed to the asadmin utility.

Before You Begin

Ensure that the following prerequisites are met:

- The Windows user is a valid user on the host to which you are testing the connection over DCOM.
- Items in the Windows operating system are set on the host as described in Windows Operating System Settings.
- The Windows user is able to run scripts on the host. For more information, see To Enable the Windows User to Run Scripts on a Remote Host.
- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- **2.** Create an alias for the Windows user's password.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for creating a password alias, see the create-password-alias(1) help page.

asadmin> create-password-alias alias-name

alias-name

Your choice of name for the alias that you are creating.

The create-password-alias subcommand prompts you to type the password for which you are creating an alias.

- **3.** In response to the prompt, type the Windows user's password.
 - The create-password-alias subcommand prompts you to type the password again.
- **4.** In response to the prompt, type the Windows user's password again.
- **5.** Create a plain text file that contains the following entry for the password alias:

AS_ADMIN_WINDOWSPASSWORD=\${ALIAS=alias-name}

alias-name

The alias name that you specified in Step 2.

Note: When you create a DCOM node, pass this file as the --passwordfile option of the asadmin utility. For more information, see To Create a DCOM Node.

Example 2-1 Creating an Alias for the Windows User's Password

This example creates an alias that is named winuser-password for the Windows user's password.

\$ asadmin create-password-alias winuser-password

Enter the alias password> Enter the alias password again> Command create-password-alias executed successfully.

The entry in the password file for the winuser-password alias is as follows:

AS_ADMIN_WINDOWSPASSWORD=\${ALIAS=winuser-password}

See Also

- asadmin(1M)
- create-password-alias(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-password-alias at the command line.

Next Steps

Test the DCOM setup as explained in To Test the Connection Over DCOM to a Remote Host.

To Test the Connection Over DCOM to a Remote Host

Testing the connection over DCOM to a remote host verifies that the required Windows services are running, the required ports are open, and the Windows user has a valid user account on the host.

Before attempting to perform any task that the requires the DAS contact the DCOM server on a remote host, test the connection over DCOM to the host. If this test fails, any attempt to perform a task that the requires the DAS contact the DCOM server on the host will also fail. Examples of such tasks are creating a DCOM node to represent the host or creating an instance that resides on the host. For more information, see To Create a DCOM Node and To Create an Instance Centrally.

If you cannot connect to the host over DCOM, troubleshoot the DCOM setup before proceeding.

Before You Begin

Ensure that the following prerequisites are met:

- The Windows user is a valid user on the host to which you are testing the connection over DCOM.
- Items in the Windows operating system are set on the host as described in Windows Operating System Settings.
- The Windows user is able to run scripts on the host. For more information, see To Enable the Windows User to Run Scripts on a Remote Host.

- Password authentication is set up for the windows user as explained in To Set Up Password Authentication for the Windows User.
- **1.** Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the validate-dcom subcommand.

Specify the file that contains the alias for the Windows user's password through the --passwordfile option of the asadmin utility. For more information about this file, see To Set Up Password Authentication for the Windows User.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the node, see the validate-dcom(1) help page.

C:\>asadmin --passwordfile filename validate-dcom host-name

The name of the file that contains the alias for the Windows user's password.

The name of the host to which you are testing the connection over DCOM.

Example 2-2 Testing the Connection Over DCOM to a Remote Host

This example tests the connection over DCOM to the host wpmd12.

C:\> asadmin --passwordfile aspwalias.txt validate-dcom wpmd12 Command validate-dcom executed successfully.

See Also

- asadmin(1M)
- validate-dcom(1)
- Windows Operating System Settings
- To Enable the Windows User to Run Scripts on a Remote Host
- To Create a DCOM Node
- To Create an Instance Centrally

You can also view the full syntax and options of the subcommand by typing asadmin help validate-dcom at the command line.

Setting Up Cygwin SSH on Windows

Set up Cygwin SSH on the DAS host and on all hosts where instances in your cluster will reside.

The following topics are addressed here:

- To Download and Install Cygwin
- To Set the Path for Windows and for the Cygwin Shell
- To Set the Home Directory for the Cygwin SSH User

To Configure and Start the Cygwin SSH Server Daemon sshd

To Download and Install Cygwin

For centralized GlassFish Server administration, a basic Cygwin installation that includes the SSH client and the SSH server daemon sshd is sufficient. The default installation options are sufficient to create such a basic installation.

- Log in as a user with Administrator privileges.
- Create the folder C:\cygwin.
- From the Cygwin home page (http://www.cygwin.com/), download and save the setup. exe file to your desktop.
- **4.** Run the setup. exe file.
- **5.** Select the default for the following options:
 - Install from Internet
 - Install Root Directory: C:\cygwin
 - Install for All Users
- **6.** Specify a folder for the local package directory that is not the Cygwin root folder, for example, C:\cygwin\packages.
- **7.** Specify the connection method.

For example, if the host is connected to the Internet through a proxy server, specify the proxy server.

- Select the mirror site from which to download the software.
- Select the openssh package for installation.
 - **a.** Under the Net category, search for openssh.
 - **b.** Locate the openssh package and click Skip.
 - The package is selected.
 - c. Click Next.

Any unsatisfied dependencies are listed.

- **10.** Leave the Select Required Packages option selected and click Next The packages are installed.
- 11. Click Finish.

See Also

For detailed information about installing Cygwin, see "Internet Setup" in Cygwin User's Guide

(http://cygwin.com/cygwin-ug-net/setup-net.html#internet-setup).

To Set the Path for Windows and for the Cygwin Shell

To enable GlassFish Server tools to find commands for SSH, each user's path for Windows and for the Cygwin shell must contain the following directories:

- The Cygwin bin directory, for example C:\cygwin\bin
- The bin directory of the JDK software

1. Log in as a user with Administrator privileges.

Logging in as a user with Administrator privileges ensures that the change applies to all users.

- **2.** In the System Information control panel, click Advanced>Environment Variables.
- **3.** Add the following directories to the Path environment variable:
 - The Cygwin bin directory, for example C:\cygwin\bin
 - The bin directory of the JDK software

To Set the Home Directory for the Cygwin SSH User

The SSH Server Daemon sshd locates a user's home directory from the configuration in the user database, not from environment variables such as HOME. To ensure that all GlassFish Server commands can run without errors, each SSH user must be configured to have a home directory.

Each user on a Windows host where SSH is set up potentially has two home directories:

- Windows home directory. GlassFish Server commands, which are run in a Windows command window, use the Windows home directory.
- **SSH home directory.** SSH commands, which are run in a shell such as bash or ksh, use the SSH home directory.

If these home directories are different, GlassFish Server and SSH each locate a user's . ssh directory in different directories. To simplify the set up of SSH, configure each user's home directory for SSH and Windows to be the same directory. A disadvantage of this approach is that the SSH home directory has spaces in its path name. Spaces in path names are cumbersome in the UNIX environment.

- 1. Log in as a user with Administrator privileges.
- 2. In the c:\cygwin\etc\passwd file, edit the home directory setting for the SSH user to specify the user's home directory for Windows.

To Configure and Start the Cygwin SSH Server Daemon sshd

Before You Begin

Ensure that the following prerequisites are met:

- A user account is created for each user that will log in to the host through SSH.
- A password is set for each user account.

The SSH server daemon sshd disallows authentication of any user for whose account a password is not set.

1. Double-click the Cygwin icon.

A Cygwin terminal is started.

- **2.** If necessary, set the password for your user account.
 - **a.** Run the passwd command as follows:
 - S passwd user-name

user-name

The user name for your account.

b. Type a password.

The password for your Windows account is also set.

- **3.** Configure SSH on the host.
 - **a.** Run the ssh-host-config command.
 - \$ ssh-host-config

Tip: If you are using Windows XP, specify the -y option of ssh-host-config to answer yes to all prompts. If you run ssh-host-config with the -y option, omit Step b.

b. Ensure that the StrictModes and PubkeyAuthentication options are set to yes in the file /etc/ssh config.

The file /etc/ssh_config can also be accessed as /cygdrive/c/cygwin/etc/sshd config.

- 4. Start the SSH server daemon sshd.
 - S net start sshd
- **5.** Confirm that the SSH server daemon sshd is running.
 - \$ cygrunsrv --query sshd

Service : sshd
Display name : CYGWIN sshd
Current State : Running Controls Accepted : Stop

Command : /usr/sbin/sshd -D

Next Steps

After you have completed the setup of SSH on a host, test the setup on the host as explained in Testing the SSH Setup on a Host.

Setting Up the MKS Toolkit on Windows

Set up the MKS Toolkit on the DAS host and on all hosts where instances in your cluster will reside.

The following topics are addressed here:

- To Install the MKS Toolkit
- To Set the Path for Windows and for the MKS Toolkit Shell
- To Set the Home Directory for the MKS Toolkit SSH User
- To Configure and Start the MKS Toolkit SSH Server Daemon sshd

To Install the MKS Toolkit

For centralized GlassFish Server administration, the default installation of the MKS Toolkit is sufficient.

Follow the instructions in the MKS Toolkit product documentation to install OpenSSH from the MKS Toolkit with default installation options.

See Also

For detailed information about installing MKS Toolkit, see "Installing MKS Toolkit" in MKS Toolkit v9.4 Release Notes

(http://www.mkssoftware.com/docs/rn/relnotes tk94.asp#install).

To Set the Path for Windows and for the MKS Toolkit Shell

To enable GlassFish Server tools to find commands for SSH, each user's path for Windows and for the MKS Toolkit shell must contain the following directories:

- The MKS Toolkit bin directory, for example C:\Program Files\MKS Toolkit\mksnt
- The bin directory of the JDK software

The MKS Toolkit installer automatically adds the MKS Toolkit bin directory to the path. However, you must add the bin directory of the JDK software to the path yourself.

- 1. Log in as a user with Administrator privileges. Logging in as a user with Administrator privileges ensures that the change applies to all users.
- **2.** In the System Information control panel, click Advanced>Environment Variables.
- Add the bin directory of the JDK software to the Path environment variable.

To Set the Home Directory for the MKS Toolkit SSH User

The SSH Server Daemon sshd locates a user's home directory from the configuration in the user database, not from environment variables such as HOME. To ensure that all GlassFish Server commands can run without errors, each SSH user must be configured to have a home directory.

Each user on a Windows host where SSH is set up potentially has two home directories:

- Windows home directory. GlassFish Server commands, which are run in a Windows command window, use the Windows home directory.
- **SSH home directory.** SSH commands, which are run in a shell such as bash or ksh, use the SSH home directory.

If these home directories are different, GlassFish Server and SSH each locate a user's . ssh directory in different directories. To simplify the set up of SSH, configure each user's home directory for SSH and Windows to be the same directory. A disadvantage of this approach is that the SSH home directory has spaces in its path name. Spaces in path names are cumbersome in the UNIX environment.

1. Compare the pairs of settings for Windows and the MKS Toolkit that are listed in the following table.

Windows Environment Variable	MKS Toolkit Field	
НОМЕРАТН	Home Directory	
HOMEDRIVE	Home Directory Drive	

- a. In a Windows command window, determine the values of the HOMEPATH and HOMEDRIVE environment variables.
- **b.** In an MKS Toolkit shell, determine the current settings of the Home Directory and Home Directory Drive fields for the user.
 - S userinfo user-name

user-name

The user name for the user whose home directory you are setting, for example Administrator.

2. If the settings do not match, update setting of each MKS Toolkit field to match its corresponding Windows environment variable.

If the settings match, no further action is required.

To update the settings, run the following command in an MKS Toolkit shell:

\$ userinfo -u -fHomeDirDrive:"drive" -fHomeDir:"path" user-name

drive

The drive identifier of the disk drive on which the user's Windows home directory resides, for example, C:.

path

The path to the user's Windows home directory, for example, \Documents and Settings\Administrator.

user-name

The user name for the user whose home directory you are setting, for example Administrator.

Note: Do not set the HOME environment variable explicitly. If Home Directory and Home Directory Drive are set correctly, the HOME environment variable specifies the correct path by default.

- **3.** In an MKS Toolkit shell, confirm that the settings were updated.
 - \$ userinfo user-name

user-name

The user name for the user whose home directory you are setting, for example Administrator.

- **4.** Log out of the host and log in to the host again.
- Confirm that the home directories are the same as explained in Step 1.

Example 2–3 Setting the Home Directory for the MKS Toolkit User

This example sets the home directory for the MKS Toolkit user Administrator to C:\Documents and Settings\Administrator.

- \$ userinfo -u -fHomeDirDrive:"C:"
- -fHomeDir:"\Documents and Settings\Administrator" Administrator

To Configure and Start the MKS Toolkit SSH Server Daemon sshd

Note: Do *not* set the command shell to cmd. exe. The use of SSH for centralized GlassFish Server administration requires a shell in the style of a UNIX shell.

- 1. From the Programs menu, choose MKS Toolkit>Configuration>Configuration Information.
- **2.** Enable password authentication and strict modes.
 - **a.** Click the Secure Shell Service tab.
 - **b.** Select the Password Authentication option.
 - **c.** Click Advanced settings.
 - **d.** Click the Login tab.
 - **e.** Deselect the Strict Modes option.
- If you are using SSH key-file authentication, enable MKSAUTH password authentication.
 - **a.** Click the Authentication tab.
 - b. Under Enable/Disable Password using MKSAUTH, type the user's password and click the Enable.
- 4. Start the SSH server daemon sshd.
- **5.** Confirm that the SSH server daemon sshd is running.

\$ service query MKSSecureSH

Name: MKS Secure Shell Service

Service Type: WIN32_OWN_PROCESS

Current State: RUNNING

Controls Accepted: ACCEPT_STOP

Check Point: 0

Wait Hint: 0
Start Type: AUTO_START Error Control: IGNORE

Path: "C:\Program Files\MKS Toolkit\bin\secshd.exe"

Dependency: NuTCRACKERService
Dependency: tcpip

Service Start Name: LocalSystem

Next Steps

After you have completed the setup of SSH on a host, test the setup on the host as explained in Testing the SSH Setup on a Host.

Setting Up SSH on UNIX and Linux Systems

Setting up SSH on UNIX and Linux systems involves verifying that the SSH server daemon sshd is running and, if necessary, starting this daemon. Set up SSH on the DAS host and on all hosts where instances in your cluster will reside.

On UNIX and Linux systems, SSH software is typically installed as part of the base operating system. If SSH is not installed, download and install the appropriate OpenSSH (http://www.openssh.com/) SSH package for your operating system. How to set up SSH on UNIX and Linux systems depends on the flavor of the operating system that you are running, as explained in the following sections:

- To Set Up SSH on Oracle Solaris Systems
- To Set Up SSH on MacOS Systems
- To Set Up SSH on Linux systems

To Set Up SSH on Oracle Solaris Systems

- 1. Ensure that the following options in the configuration file /etc/ssh/sshd_config are set to yes:
 - StrictModes
 - PubkeyAuthentication
- 2. Determine if the SSH server daemon sshd is running.
 - \$ /usr/bin/svcs ssh
- **3.** If the SSH server daemon sshd is not running, start this daemon.

If the daemon is running, no further action is required.

\$ /usr/sbin/svcadm enable ssh

Example 2-4 Determining if the sshd Daemon Is Running on an Oracle Solaris System

This example confirms that the SSH server daemon sshd is running on an Oracle Solaris system.

\$ /usr/bin/svcs ssh

```
STATE STIME FMRI
         Jul_06 svc:/network/ssh:default
online
```

See Also

svcs(1)

Next Steps

After you have completed the setup of SSH on a host, test the setup on the host as explained in Testing the SSH Setup on a Host.

To Set Up SSH on MacOS Systems

- 1. Open System Preferences and click Sharing.
 - The Sharing window opens.
- **2.** Ensure that Remote Login is selected in the Service list.
- **3.** Ensure that either of the following is allowed access:
 - All Users
 - The user that running the DAS or instance
- (MacOS 10.6 systems only) Ensure that the SSH server daemon sshd allows password authentication.

On MacOS 10.5 systems, the SSH server daemon sshd allows password authentication by default. However, on MacOS 10.6 systems, the SSH server daemon sshd disallows password authentication by default.

- **a.** Edit the configuration file /etc/sshd_config to set the PasswordAuthentication option to yes.
- **b.** Stop the SSH server daemon sshd.
 - \$ sudo launchctl stop com.openssh.sshd
- **c.** Start the SSH server daemon sshd.
 - \$ sudo launchctl start com.openssh.sshd

Next Steps

After you have completed the setup of SSH on a host, test the setup on the host as explained in Testing the SSH Setup on a Host.

To Set Up SSH on Linux systems

- 1. Ensure that the following options in the configuration file /etc/ssh/sshd_config are set to yes:
 - StrictModes
 - PubkeyAuthentication
- **2.** Determine if the SSH server daemon sshd is running.
 - \$ /sbin/service sshd status
- **3.** If the SSH server daemon sshd is not running, start this daemon.

If the daemon is running, no further action is required.

\$ /sbin/service sshd start

Example 2-5 Determining if the sshd Daemon Is Running on a Linux System

This example confirms that the SSH server daemon sshd is running on a Linux system.

```
$ /sbin/service sshd status
openssh-daemon (pid 2373) is running...
```

Next Steps

After you have completed the setup of SSH on a host, test the setup on the host as explained in Testing the SSH Setup on a Host.

Testing the SSH Setup on a Host

After setting up SSH on a host, test the setup to ensure that you can use SSH to contact the host from another host. Testing the SSH setup on a host verifies that the SSH server daemon sshd is running and that the SSH user has a valid user account on the host.

If you cannot use SSH to contact the host, troubleshoot the SSH setup before setting up SSH user authentication.

To Test the SSH Setup on a Host

1. From another host, use SSH to log in into the host that you are testing as the SSH

\$ ssh -1 user-name host-name

user-name

The user name for the SSH user's account on the host.

host-name

The host name of the host that you are logging in to.

2. In response to the prompt, type your password.

If this step succeeds, your setup of SSH is complete.

The first time that you connect to a host, you might be warned that the authenticity cannot be established and be asked if you want to continue connection. If you trust the host, answer yes to connect to the host.

Troubleshooting

To obtain diagnostic information, use the -v option of the command-line SSH client and the -d option of the SSH server daemon sshd. How to start the SSH server daemon sshd manually depends on the operating system and SSH provider that you are using.

If the SSH server daemon sshd is set up on a host that has a firewall, ensure that a rule is defined to allow inbound traffic on the SSH port. The default SSH port is port 22.

If your connection is refused, the SSH server daemon sshd is not running and you must start the daemon. For instructions, see the following sections:

- To Configure and Start the Cygwin SSH Server Daemon sshd
- To Configure and Start the MKS Toolkit SSH Server Daemon sshd
- To Set Up SSH on Oracle Solaris Systems

If your connection is accepted, but you cannot log in, ensure that the SSH user has a valid user account on the host.

Next Steps

After testing the SSH setup, set up SSH user authentication to enable SSH to authenticate users without prompting for a password. For more information, see Setting Up SSH User Authentication.

Setting Up SSH User Authentication

When a GlassFish Server subcommand uses SSH to log in to a remote host, GlassFish Server must be able to authenticate the SSH user. Setting up SSH user authentication ensures that this requirement is met.

Before setting up SSH user authentication, determine the authentication scheme to use. If SSH is already deployed at your site, the authentication scheme to use might already be chosen for you.

The following table lists the authentication schemes that GlassFish Server supports. The table also lists the advantages and disadvantages of each authentication scheme.

Authentication Scheme	Advantages	Disadvantages		
Public key without encryption	GlassFish Server provides tools to simplify set up.	SSH must be configured to locate users' key files in the correct location. File access permissions for key files and the directory that contains the key files must be set correctly.		
Public key with passphrase-protected encryption	This scheme is more secure than public key authentication without encryption.	SSH must be configured to locate users' key files in the correct location. File access permissions for key files and the directory that contains the key files must be set correctly. For each SSH user, GlassFish Server password aliases are required for the encryption passphrase.		
Password	No SSH configuration is required to locate key files or to ensure that file access permissions are correct.	For each SSH user, GlassFish Server password aliases are required for the SSH password.		

The following topics are addressed here:

- To Set Up Public Key Authentication Without Encryption
- To Set Up Encrypted Public Key Authentication
- To Set Up Password Authentication

To Set Up Public Key Authentication Without Encryption

Use the setup-ssh subcommand in local mode to set up public key authentication without encryption. This subcommand enables you to set up public key authentication on multiple hosts in a single operation.

The setup-ssh subcommand generates a key pair and distributes the public key file to specified hosts. The private key file and the public key file are protected only by the file system's file access permissions. If you require additional security, set up public key authentication with passphrase-protected encryption as explained in To Set Up Encrypted Public Key Authentication.

Before You Begin

Ensure that the following prerequisites are met:

- SSH is set up on each host where you are setting up public key authentication. For more information, see the following sections:
 - Setting Up Cygwin SSH on Windows
 - Setting Up the MKS Toolkit on Windows
 - Setting Up SSH on UNIX and Linux Systems
- Only the SSH user has write access to the following files and directories on each host where you are setting up public key authentication:
 - The SSH user's home directory
 - The ~/.ssh directory

The authorized_key file

If other users can write to these files and directories, the secure service might not trust the authorized_key file and might disallow public key authentication.

1. Generate an SSH key pair and distribute the public key file to the hosts where you are setting up public key authentication.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for setting up an SSH key, see the setup-ssh(1) help page.

```
asadmin> setup-ssh [--sshuser sshuser] host-list
```

sshuser

The SSH user for which you are generating the SSH key pair. If you are running the subcommand as the SSH user, you may omit this option.

A space-separated list of the names of the hosts where the SSH public key is to be distributed.

After generating the SSH key pair, the subcommand uses SSH to log in to each host in *host-list* as the SSH user to distribute the public key. Each time a password is required to log in to a host, you are prompted for the SSH user's password.

In response to each prompt for a password, type the SSH user's password.

Example 2–6 Setting Up Public Key Authentication Without Encryption

This example generates and sets up an SSH key for the user gfuser on the hosts sua01 and sua02. The command is run by the user gfuser.

```
asadmin> setup-ssh --generatekey=true sua01 sua02
Enter SSH password for gfuser@sua01>
Created directory /home/gfuser/.ssh
/usr/bin/ssh-keygen successfully generated the identification
/home/gfuser/.ssh/id_rsa
Copied keyfile /home/gfuser/.ssh/id_rsa.pub to gfuser@sua01
Successfully connected to gfuser@sua01 using keyfile /home/gfuser/.ssh/id_rsa
Copied keyfile /home/gfuser/.ssh/id_rsa.pub to gfuser@sua02
Successfully connected to gfuser@sua02 using keyfile /home/gfuser/.ssh/id_rsa
Command setup-ssh executed successfully.
```

Next Steps

After setting up public key authentication, test the setup by using ssh to log in as the SSH user to each host where the public key was distributed. For each host, log in first with the unqualified host name and then with the fully qualified name. If SSH does *not* prompt for password, public key authentication is set up correctly on the host.

If you are prompted for a password, verify that the public key file was copied correctly to the SSH user's authorized_keys file.

Troubleshooting

Setup might fail because file access permissions in the SSH user's home directory are too permissive. In this situation, ensure that the file access permissions in the SSH user's home directory meet the requirements for performing this procedure.

If you have set the file access permissions in the SSH user's home directory correctly, setup might still fail if you are using the MKS Toolkit. In this situation, correct the problem in one of the following ways:

- On each remote host, copy the public key file to the SSH user's ~/.ssh directory and import the file. To import the file, select the Secure Service tab in the MKS configuration GUI and click Passwordless.
- Disable strict modes.

See Also

- Setting Up Cygwin SSH on Windows
- Setting Up the MKS Toolkit on Windows
- Setting Up SSH on UNIX and Linux Systems
- setup-ssh(1)

You can also view the full syntax and options of the subcommand by typing asadmin help setup-ssh at the command line.

To Set Up Encrypted Public Key Authentication

Encrypted key file authentication uses an encrypted private key file that is protected with a passphrase. This passphrase must be provided to use the private key to unlock the public key. If you require encrypted public key authentication, you must use the SSH utility ssh-keygen to generate an SSH key pair with an encrypted private key. You can then use the setup-ssh subcommand to distribute the public key file to specified hosts.

To use the encrypted key file, GlassFish Server requires the passphrase with which the key file was encrypted. To provide this passphrase securely to GlassFish Server, create a GlassFish Server password alias to represent the passphrase and store this alias in a password file that is passed to the asadmin utility.

Note: Only the options that are required to complete this task are provided in each step. For information about all the options for the commands and subcommands in this task, see their help pages or man pages.

Before You Begin

Ensure that the following prerequisites are met:

- SSH is set up on each host where you are setting up public key authentication. For more information, see the following sections:
 - Setting Up Cygwin SSH on Windows
 - Setting Up the MKS Toolkit on Windows
 - Setting Up SSH on UNIX and Linux Systems
- Only the SSH user has write access to the following files and directories on each host where you are setting up public key authentication:

- The SSH user's home directory
- The ~/.ssh directory
- The authorized key file

If other users can write to these files and directories, the secure service might not trust the authorized_key file and might disallow public key authentication.

1. Generate an SSH key pair with an encrypted private key file.

Use the SSH utility ssh-keygen for this purpose.

```
$ ssh-keygen -t type
```

type

The algorithm that is to be used for the key and which must be rsa, dsa, or rsa1.

The ssh-keygen utility prompts you for a file in which to save the key.

To simplify the distribution of the key file, accept the default file.

The ssh-keygen utility prompts you for a passphrase.

3. In response to the prompt, type your choice of passphrase for encrypting the private key file.

The ssh-keygen utility prompts you to type the passphrase again.

- In response to the prompt, type the passphrase that you set in Step 3.
- Distribute the public key file to the hosts where you are setting up public key authentication.

Use the setup-ssh asadmin subcommand for this purpose.

```
$ asadmin setup-ssh --generatekey=false host-list
```

host-list

A space-separated list of the names of the hosts where the SSH public key is to be distributed.

The subcommand uses SSH to log in to each host in host-list as the SSH user to distribute the public key. Each time a passphrase or a password is required to log in to a host, you are prompted for the passphrase or the SSH user's password.

- **6.** In response to each prompt, type the requested information.
 - In response to each prompt for a passphrase, type the passphrase that you set in Step 3.
 - In response to each prompt for a password, type the SSH user's password.
- 7. Create a GlassFish Server password alias for the passphrase that you set in Step 3.
 - **a.** Ensure that the DAS is running.

Remote subcommands require a running server.

b. Run the create-password-alias asadmin subcommand.

```
S asadmin create-password-alias alias-name
```

alias-name

Your choice of name for the alias that you are creating.

- The create-password-alias subcommand prompts you to type the passphrase for which you are creating an alias.
- **c.** In response to the prompt, type the passphrase that you set in Step 3. The create-password-alias subcommand prompts you to type the passphrase again.
- **d.** In response to the prompt, type the passphrase that you set in Step 3 again.
- Create a plain text file that contains the following entry for the passphrase alias:

```
AS_ADMIN_SSHKEYPASSPHRASE=${ALIAS=alias-name}
```

alias-name

The alias name that you specified in Step 7.

Note: When you create an SSH node, pass this file as the --passwordfile option of the asadmin utility. For more information, see To Create an SSH Node.

Example 2–7 Setting Up Encrypted Public Key Authentication

This example generates an SSH key pair with an encrypted private key for the user gfadmin and distributes the public key to the hosts sj01 and ja02. The example also creates an alias that is named ssh-key-passphrase for the private key's passphrase.

\$ ssh-keygen -t rsa

```
Generating public/private rsa key pair.
Enter file in which to save the key (/home/gfadmin/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /home/gfadmin/.ssh/id_rsa.
Your public key has been saved in /home/gfadmin/.ssh/id_rsa.pub.
The key fingerprint is:
db:b5:f6:0d:fe:16:33:91:20:64:90:1a:84:66:f5:d0 gfadmin@dashost
$ asadmin setup-ssh --generatekey=false sj01 sj02
Key /home/gfadmin/.ssh/id_rsa is encrypted
Enter key passphrase>
Enter SSH password for gfadmin@sj01>
Copied keyfile /home/gfadmin/.ssh/id_rsa.pub to gfadmin@sj01
Successfully connected to gfadmin@sj01 using keyfile /home/gfadmin/.ssh/id_rsa
Successfully connected to gfadmin@sj02 using keyfile /home/gfadmin/.ssh/id rsa
SSH public key authentication is already configured for gfadmin@sj02
Command setup-ssh executed successfully.
$ asadmin create-password-alias ssh-key-passphrase
Enter the alias password>
Enter the alias password again>
```

The entry in the password file for the ssh-key-passphrase alias is as follows:

```
AS_ADMIN_SSHKEYPASSPHRASE=${ALIAS=ssh-key-passphrase}
```

Command create-password-alias executed successfully.

Troubleshooting

Setup might fail because file access permissions in the SSH user's home directory are too permissive. In this situation, ensure that the file access permissions in the SSH user's home directory meet the requirements for performing this procedure.

If you have set the file access permissions in the SSH user's home directory correctly, setup might still fail if you are using the MKS Toolkit. In this situation, correct the problem in one of the following ways:

- On each remote host, copy the public key file to the SSH user's ~/.ssh directory and import the file. To import the file, select the Secure Service tab in the MKS configuration GUI and click Passwordless.
- Disable strict modes.

See Also

- Setting Up Cygwin SSH on Windows
- Setting Up the MKS Toolkit on Windows
- Setting Up SSH on UNIX and Linux Systems
- asadmin(1M)
- create-password-alias(1)
- setup-ssh(1)
- ssh-keygen(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help create-password-alias
- asadmin help setup-ssh

To Set Up Password Authentication

To use SSH to log in to a remote host, GlassFish Server requires the SSH user's password. To provide this password securely to GlassFish Server, create a GlassFish Server password alias to represent the password and store this alias in a password file that is passed to the asadmin utility.

Before You Begin

Ensure that SSH is set up on each host where you are setting up password authentication. For more information, see the following sections:

- Setting Up Cygwin SSH on Windows
- Setting Up the MKS Toolkit on Windows
- Setting Up SSH on UNIX and Linux Systems
- Ensure that the DAS is running.

Remote subcommands require a running server.

2. Create an alias for the SSH user's password.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for creating a password alias, see the create-password-alias(1) help page.

asadmin> create-password-alias alias-name

alias-name

Your choice of name for the alias that you are creating.

The create-password-alias subcommand prompts you to type the password for which you are creating an alias.

3. In response to the prompt, type the SSH user's password.

The create-password-alias subcommand prompts you to type the password again.

- In response to the prompt, type the SSH user's password again.
- **5.** Create a plain text file that contains the following entry for the password alias:

AS_ADMIN_SSHPASSWORD=\${ALIAS=alias-name}

alias-name

The alias name that you specified in Step 2.

Note: When you create an SSH node, pass this file as the --passwordfile option of the asadmin utility. For more information, see To Create an SSH Node.

Example 2-8 Creating an Alias for the SSH User's Password

This example creates an alias that is named ssh-password for the SSH user's password.

\$ asadmin create-password-alias ssh-password

Enter the alias password> Enter the alias password again> Command create-password-alias executed successfully.

The entry in the password file for the ssh-password alias is as follows:

AS_ADMIN_SSHPASSWORD=\${ALIAS=ssh-password}

See Also

- Setting Up Cygwin SSH on Windows
- Setting Up the MKS Toolkit on Windows
- Setting Up SSH on UNIX and Linux Systems
- asadmin(1M)
- create-password-alias(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-password-alias at the command line.

Installing and Removing GlassFish Server Software on Multiple Hosts

GlassFish Server software must be installed on all hosts where GlassFish Server will run. How to install GlassFish Server software on multiple hosts depends on the degree of control that you require over the installation on each host.

If you require complete control over the installation on each host, install the software from a GlassFish Server distribution on each host individually. For more information, see GlassFish Server Open Source Edition Installation Guide.

If the same set up on each host is acceptable, copy an existing GlassFish Server installation to the hosts. For more information, see To Copy a GlassFish Server Installation to Multiple Hosts.

GlassFish Server also enables you to remove GlassFish Server software from multiple hosts in a single operation. For more information, see To Remove GlassFish Server Software From Multiple Hosts.

The following topics are addressed here:

- To Copy a GlassFish Server Installation to Multiple Hosts
- To Remove GlassFish Server Software From Multiple Hosts

To Copy a GlassFish Server Installation to Multiple Hosts

Use the install-node-dcom subcommand or the install-node-ssh subcommand in local mode to copy an installation of GlassFish Server software to multiple hosts.

Before You Begin

Ensure that DCOM or SSH is set up on the host where you are running the subcommand and on each host where you are copying the GlassFish Server software.

Run the appropriate subcommand for the protocol that is set up for communication between the hosts.

If DCOM is set up for communication between the hosts, run the install-node-dcom subcommand.

> **Note:** Only the options that are required to complete this task are provided in this step. For information about all the options for copying an installation of GlassFish Server software, see the install-node-dcom(1) help page.

asadmin> install-node-dcom host-list

host-list

A space-separated list of the names of the hosts where you are copying the installation of GlassFish Server software.

If SSH is set up for communication between the hosts, run the install-node-ssh subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for copying an installation of GlassFish Server software, see the install-node-ssh(1) help page.

asadmin> install-node-ssh host-list

host-list

A space-separated list of the names of the hosts where you are copying the installation of GlassFish Server software.

Example 2-9 Copying a GlassFish Server Installation to Multiple DCOM-Enabled Hosts

This example copies the GlassFish Server software on the host where the subcommand is run to the default location on the DCOM-enabled hosts wpmdll.example.com and wpmd12.example.com.

Some lines of output are omitted from this example for readability.

```
asadmin> install-node-dcom wpmdl1.example.com wpmdl2.example.com
Created installation zip C:\glassfish8107276692860773166.zip
Copying 85760199 bytes.....
WROTE FILE TO REMOTE SYSTEM: C:/glassfish3/glassfish_install.zip and
C:/glassfish3/unpack.bat
Output from Windows Unpacker:
C:\Windows\system32>C:
C:\Windows\system32>cd "C:\glassfish3"
C:\glassfish3>jar xvf glassfish_install.zip
inflated: bin/asadmin
inflated: bin/asadmin.bat
inflated: glassfish/bin/appclient
inflated: glassfish/bin/appclient.bat
 inflated: glassfish/bin/appclient.js
 inflated: glassfish/bin/asadmin
 inflated: glassfish/bin/asadmin.bat
 inflated: mq/lib/props/broker/default.properties
 inflated: mq/lib/props/broker/install.properties
Command install-node-dcom executed successfully.
```

Example 2-10 Copying a GlassFish Server Installation to Multiple SSH-Enabled Hosts

This example copies the GlassFish Server software on the host where the subcommand is run to the default location on the SSH-enabled hosts sj03.example.com and si04.example.com.

```
asadmin> install-node-ssh sj03.example.com sj04.example.com
Created installation zip /home/gfuser/glassfish2339538623689073993.zip
Successfully connected to gfuser@sj03.example.com using keyfile /home/gfuser
/.ssh/id rsa
Copying /home/gfuser/glassfish2339538623689073993.zip (81395008 bytes) to
sj03.example.com:/export/glassfish3
Installing glassfish2339538623689073993.zip into
sj03.example.com:/export/glassfish3
Removing sj03.example.com:/export/glassfish3/glassfish2339538623689073993.zip
Fixing file permissions of all files under sj03.example.com:/export/glassfish3/bin
Successfully connected to gfuser@sj04.example.com using keyfile /home/gfuser
/.ssh/id_rsa
Copying /home/gfuser/glassfish2339538623689073993.zip (81395008 bytes) to
sj04.example.com:/export/glassfish3
Installing glassfish2339538623689073993.zip into
sj04.example.com:/export/glassfish3
Removing sj04.example.com:/export/glassfish3/glassfish2339538623689073993.zip
Fixing file permissions of all files under sj04.example.com:/export/glassfish3/bin
Command install-node-ssh executed successfully
```

See Also

- install-node-dcom(1)
- install-node-ssh(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help install-node-dcom
- asadmin help install-node-ssh

To Remove GlassFish Server Software From Multiple Hosts

Use the uninstall-node-dcom subcommand or the uninstall-node-ssh subcommand in local mode to remove GlassFish Server software from multiple hosts.

Before You Begin

Ensure that the following prerequisites are met:

- DCOM or SSH is set up on the host where you are running the subcommand and on each host from which you are removing the GlassFish Server software.
- No process is accessing the parent of the base installation directory for the GlassFish Server software or any subdirectory of this directory.
- The parent of the base installation directory for the GlassFish Server software is the same on each host from which you are removing the GlassFish Server software.
- For hosts that use DCOM for remote communication, the configuration of the following items is the same on each host:
 - Windows Domain
 - Windows User
- For hosts that use SSH for remote communication, the configuration of the following items is the same on each host:
 - SSH port
 - SSH user
 - SSH key file

Run the appropriate subcommand for the protocol that is set up for communication between the hosts.

If DCOM is set up for communication between the hosts, run the uninstall-node-dcom subcommand.

> **Note:** Only the options that are required to complete this task are provided in this step. For information about all the options for removing GlassFish Server software, see the uninstall-node-dcom(1) help page.

asadmin> uninstall-node-dcom host-list

host-list

A space-separated list of the names of the hosts from which you are removing GlassFish Server software.

If SSH is set up for communication between the hosts, run the uninstall-node-ssh subcommand.

> **Note:** Only the options that are required to complete this task are provided in this step. For information about all the options for removing GlassFish Server software, see the uninstall-node-ssh(1) help page.

asadmin> uninstall-node-ssh host-list

host-list

A space-separated list of the names of the hosts from which you are removing GlassFish Server software.

Example 2–11 Removing GlassFish Server Software From Multiple DCO\M-Enabled Hosts

This example removes GlassFish Server software on the DCOM-enabled hosts wpmdll.example.com and wpmdll.example.com from the default location.

asadmin> uninstall-node-dcom wpmdl1 wpmdl2 Command uninstall-node-dcom executed successfully.

Example 2-12 Removing GlassFish Server Software From Multiple SSH-Enabled Hosts

This example removes GlassFish Server software on the SSH-enabled hosts sj03.example.com and sj04.example.com from the default location.

asadmin> uninstall-node-ssh sj03 sj04

Successfully connected to gfuser@sj03.example.com using keyfile /home/gfuser /.ssh/id_rsa

Successfully connected to gfuser@sj04.example.com using keyfile /home/gfuser /.ssh/id rsa

Command uninstall-node-ssh executed successfully.

See Also

- uninstall-node-dcom(1)
- uninstall-node-ssh(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help uninstall-node-dcom
- asadmin help uninstall-node-ssh

Administering GlassFish Server Nodes

A node represents a host on which the GlassFish Server software is installed. A node must exist for every host on which GlassFish Server instances reside. A node's configuration contains information about the host such as the name of the host and the location where the GlassFish Server is installed on the host.

The following topics are addressed here:

- Types of GlassFish Server Nodes
- Creating, Listing, Testing, and Deleting DCOM Nodes
- Creating, Listing, Testing, and Deleting SSH Nodes
- Creating, Listing, and Deleting CONFIG Nodes
- Updating and Changing the Type of a Node

Types of GlassFish Server Nodes

Each GlassFish Server node is one of the following types of node:

DCOM

A DCOM node supports communication over the Distributed Component Object Model (DCOM) remote protocol. The DCOM remote protocol is available only on Windows systems. If DCOM is set up and you plan to administer your GlassFish Server instances centrally, the instances *must* reside on DCOM nodes.

A DCOM node's configuration contains the information that is required to connect to the host through DCOM. This information includes, for example, the user name of the Windows user and the port number for DCOM connections to the host.

An SSH node supports communication over secure shell (SSH). If SSH is set up and you plan to administer your GlassFish Server instances centrally, the instances *must* reside on SSH nodes.

An SSH node's configuration contains the information that is required to connect to the host through SSH. This information includes, for example, the user name of the SSH user and the port number for SSH connections to the host.

CONFIG

A CONFIG node does not support remote communication. If neither DCOM nor SSH is set up and you plan to administer your instances locally, the instances can reside on CONFIG nodes. You cannot use CONFIG nodes for instances that you plan to administer centrally.

Each domain contains a predefined CONFIG node that is named localhost-domain, where domain is the name of the domain. On the host where the domain administration server (DAS) is running, this node represents the local host.

Creating, Listing, Testing, and Deleting DCOM Nodes

A DCOM node supports communication over DCOM. If DCOM is set up and you plan to administer your GlassFish Server instances centrally, the instances must reside on DCOM nodes. For information about setting up DCOM, see Enabling Centralized Administration of GlassFish Server Instances.

GlassFish Server enables you to create DCOM nodes for use by instances, obtain information about DCOM nodes, test if DCOM nodes are reachable, and delete DCOM nodes that are no longer required.

The following topics are addressed here:

- To Create a DCOM Node
- To List DCOM Nodes in a Domain
- To Test if a DCOM Node is Reachable
- To Delete a DCOM Node

To Create a DCOM Node

Use the create-node-dcom subcommand in remote mode to create a DCOM node.

Before You Begin

Ensure that the Windows user can use DCOM to connect to the host that the node will represent. By default, the create-node-dcom subcommand validates the node's parameters and the DCOM connection to the host. If the Windows user cannot use DCOM to connect to the host, the validation fails.

Note: For information about how to determine whether the Windows user can use DCOM to connect to the host, see To Test the Connection Over DCOM to a Remote Host.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the create-node-dcom subcommand.

Specify the file that contains the alias for the Windows user's password through the --passwordfile option of the asadmin utility. For more information about this file, see To Set Up Password Authentication for the Windows User.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the node, see the create-node-dcom(1) help page.

```
C:\> asadmin --passwordfile filename create-node-dcom
--nodehost node-host [--installdir install-dir ]
node-name
```

filname

The name of the file that contains the alias for the Windows user's password.

The name of the host that the node represents. The name of the host must be specified. Otherwise, an error occurs.

install-dir

The full path to the parent of the base installation directory of the GlassFish Server software on the host, for example, C:\glassfish3. If the GlassFish Server software is installed in the same directory on the node's host and the DAS host, you can omit this option.

node-name

Your choice of name for the node that you are creating.

Example 3-1 Creating a DCOM Node

This example creates the DCOM node wpmdl1 to represent the host wpmdl1.example.com. The GlassFish Server software is installed in the same directory on the DAS host and on the host wpmdll.example.com.

```
C:\> asadmin --passwordfile aspwalias.txt create-node-dcom
--nodehost wpmdl1.example.com wpmdl1
Command create-node-dcom executed successfully.
```

See Also

- asadmin(1M)
- create-node-dcom(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-node-dcom at the command line.

Next Steps

After creating a node, you can create instances on the node as explained in the following sections:

- To Create an Instance Centrally
- To Create an Instance Locally

To List DCOM Nodes in a Domain

Use the list-nodes-dcom subcommand in remote mode to obtain information about existing DCOM nodes in a domain.

Note: To obtain information about all existing nodes in a domain, use the list-nodes subcommand.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the list-nodes-dcom subcommand.

asadmin> list-nodes-dcom

Example 3–2 Listing Basic Information About All DCOM Nodes in a Domain

This example lists the name, type, and host of all DCOM nodes in the current domain.

```
asadmin> list-nodes-dcom
xkyd DCOM xkyd.example.com
wpmd12 DCOM wpmd12.example.com
wpmdl1 DCOM wpmdl1.example.com
Command list-nodes-dcom executed successfully.
```

Example 3–3 Listing Detailed Information About All DCOM Nodes in a Domain

This example lists detailed information about all DCOM nodes in the current domain.

asadmin> list-nodes-dcom --long=true NODE NAME TYPE NODE HOST INSTALL DIRECTORY REFERENCED BY xkyd DCOM xkyd.example.com C:\glassfish3 wpmd12 DCOM wpmd12.example.com C:\glassfish3 wdi2 wpmd11 DCOM wpmd11.example.com C:\glassfish3 wdi1 Command list-nodes-dcom executed successfully.

See Also

- list-nodes(1)
- list-nodes-dcom(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help list-nodes
- asadmin help list-nodes-dcom

To Test if a DCOM Node is Reachable

Use the ping-node-dcom subcommand in remote mode to test if a DCOM node is reachable.

Before You Begin

Ensure that DCOM is configured on the host where the DAS is running and on the host that the node represents.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the ping-node-dcom subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for testing the node, see the ping-node-dcom(1) help page.

```
asadmin> ping-node-dcom node-name
```

node-name

The name of the node to test.

Example 3-4 Testing if a DCOM Node Is Reachable

This example tests if the DCOM node wpmd12 is reachable.

```
asadmin> ping-node-dcom wpmd12
Successfully made DCOM connection to node wpmdl2 (wpmdl2.example.com)
Command ping-node-dcom executed successfully.
```

See Also

ping-node-dcom(1)

You can also view the full syntax and options of the subcommand by typing asadmin help ping-node-dcom at the command line.

To Delete a DCOM Node

Use the delete-node-dcom subcommand in remote mode to delete a DCOM node.

Deleting a node removes the node from the configuration of the DAS. The node's directories and files are deleted when the last GlassFish Server instance that resides on the node is deleted.

Before You Begin

Ensure that no GlassFish Server instances reside on the node that you are deleting. For information about how to delete an instance, see the following sections.

- To Delete an Instance Centrally
- To Delete an Instance Locally
- Ensure that the DAS is running.

Remote subcommands require a running server.

2. Confirm that no instances reside on the node that you are deleting.

```
asadmin> list-nodes-dcom --long=true
```

3. Run the delete-node-dcom subcommand.

```
asadmin> delete-node-dcom node-name
```

node-name

The name of the node that you are deleting.

Example 3-5 Deleting a DCOM Node

This example confirms that no instances reside on the DCOM node xkyd and deletes the node xkyd.

asadmin> list-nodes-dcom --long=true NODE NAME TYPE NODE HOST INSTALL DIRECTORY REFERENCED BY xkyd DCOM xkyd.example.com C:\glassfish3 wpmdl2 DCOM wpmdl2.example.com C:\glassfish3 wpmdl1 DCOM wpmdl1.example.com C:\glassfish3 wdi2 wdi1 Command list-nodes-dcom executed successfully. asadmin> delete-node-dcom xkyd Command delete-node-dcom executed successfully.

See Also

- To Delete an Instance Centrally
- To Delete an Instance Locally
- delete-node-dcom(1)
- list-nodes-dcom(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-node-dcom
- asadmin help list-nodes-dcom

Creating, Listing, Testing, and Deleting ssн Nodes

An SSH node supports communication over SSH. If SSH is set up and you plan to administer your GlassFish Server instances centrally, the instances must reside on SSH nodes. For information about setting up SSH, see Enabling Centralized Administration of GlassFish Server Instances.

Note: Windows systems also support communications over DCOM as an alternative to SSH.

GlassFish Server enables you to create SSH nodes for use by instances, obtain information about SSH nodes, test if SSH nodes are reachable, and delete SSH nodes that are no longer required.

The following topics are addressed here:

- To Create an SSH Node
- To List SSH Nodes in a Domain
- To Test if an SSH Node is Reachable
- To Delete an SSH Node

To Create an ssн Node

Use the create-node-ssh subcommand in remote mode to create an SSH node.

Before You Begin

Ensure that the SSH user can use SSH to log in to the host that the node will represent. By default, the create-node-ssh subcommand validates the node's parameters and the SSH connection to the host. If the SSH user cannot use SSH to log in to the host, the validation fails.

- Ensure that the DAS is running. Remote subcommands require a running server.
- **2.** Run the create-node-ssh subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the node, see the create-node-ssh(1) help page.

If you are using password authentication for the SSH user, you must specify a password file through the --passwordfile option of the asadmin utility. For more information about SSH user authentication, see Setting Up SSH User Authentication.

asadmin> create-node-ssh --nodehost node-host [--installdir install-dir] node-name

node-host

The name of the host that the node represents. The name of the host must be specified. Otherwise, an error occurs.

install-dir

The full path to the parent of the base installation directory of the GlassFish Server software on the host, for example, /export/glassfish3/. If the GlassFish Server software is installed in the same directory on the node's host and the DAS host, you can omit this option.

node-name

Your choice of name for the node that you are creating.

Example 3–6 Creating an SSH Node

This example creates the SSH node sj01 to represent the host sj01.example.com. The GlassFish Server software is installed in the same directory on the DAS host and on the host sj01.example.com.

asadmin> create-node-ssh --nodehost sj01.example.com sj01 Command create-node-ssh executed successfully.

Troubleshooting

The create-node-ssh subcommand might fail to create the node and report the error Illegal sftp packet len. If this error occurs, ensure that no the startup file on the remote host displays text for noninteractive shells. Examples of startup files are .bashrc, .cshrc, .login, and .profile.

The SSH session interprets any text message that is displayed during login as a file-transfer protocol packet. Therefore, any statement in a startup file that displays text messages corrupts the SSH session, causing this error.

See Also

create-node-ssh(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-node-ssh at the command line.

Next Steps

After creating a node, you can create instances on the node as explained in the following sections:

To Create an Instance Centrally

To Create an Instance Locally

To List ssн Nodes in a Domain

Use the list-nodes-ssh subcommand in remote mode to obtain information about existing SSH nodes in a domain.

Note: To obtain information about all existing nodes in a domain, use the list-nodes subcommand.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the list-nodes-ssh subcommand.

```
asadmin> list-nodes-ssh
```

Example 3–7 Listing Basic Information About All SSH Nodes in a Domain

This example lists the name, type, and host of all SSH nodes in the current domain.

```
asadmin> list-nodes-ssh
sj01 SSH sj01.example.com
sj02 SSH sj02.example.com
Command list-nodes-ssh executed successfully.
```

Example 3–8 Listing Detailed Information About All SSH Nodes in a Domain

This example lists detailed information about all SSH nodes in the current domain.

```
asadmin> list-nodes-ssh --long=true
NODE NAME TYPE NODE HOST INSTALL DIRECTORY REFERENCED BY
sj01 SSH sj01.example.com /export/glassfish3 pmd-i1 sj02 SSH sj02.example.com /export/glassfish3 pmd-i2
Command list-nodes-ssh executed successfully.
```

See Also

- list-nodes(1)
- list-nodes-ssh(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help list-nodes
- asadmin help list-nodes-ssh

To Test if an SSH Node is Reachable

Use the ping-node-ssh subcommand in remote mode to test if an SSH node is reachable.

Before You Begin

Ensure that SSH is configured on the host where the DAS is running and on the host that the node represents.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the ping-node-ssh subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for testing the node, see the ping-node-ssh(1) help page.

asadmin> ping-node-ssh node-name

node-name

The name of the node to test.

Example 3-9 Testing if an SSH Node Is Reachable

This example tests if the SSH node sj01 is reachable.

```
asadmin> ping-node-ssh sj01
Successfully made SSH connection to node sj01 (sj01.example.com)
Command ping-node-ssh executed successfully.
```

See Also

ping-node-ssh(1)

You can also view the full syntax and options of the subcommand by typing asadmin help ping-node-ssh at the command line.

To Delete an ssн Node

Use the delete-node-ssh subcommand in remote mode to delete an SSH node.

Deleting a node removes the node from the configuration of the DAS. The node's directories and files are deleted when the last GlassFish Server instance that resides on the node is deleted.

Before You Begin

Ensure that no GlassFish Server instances reside on the node that you are deleting. For information about how to delete an instance, see the following sections.

- To Delete an Instance Centrally
- To Delete an Instance Locally
- Ensure that the DAS is running.

Remote subcommands require a running server.

Confirm that no instances reside on the node that you are deleting.

```
asadmin> list-nodes-ssh --long=true
```

Run the delete-node-ssh subcommand.

```
asadmin> delete-node-ssh node-name
```

node-name

The name of the node that you are deleting.

Example 3-10 Deleting an SSH Node

This example confirms that no instances reside on the SSH node sj01 and deletes the node sj01.

```
asadmin> list-nodes-ssh --long=true
NODE NAME TYPE NODE HOST
                                                     REFERENCED BY
                           INSTALL DIRECTORY
sj01 SSH sj01.example.com /export/glassfish3
        SSH sj02.example.com /export/glassfish3 pmd-i2
Command list-nodes-ssh executed successfully.
asadmin> delete-node-ssh sj01
Command delete-node-ssh executed successfully.
```

See Also

- To Delete an Instance Centrally
- To Delete an Instance Locally
- delete-node-ssh(1)
- list-nodes-ssh(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-node-ssh
- asadmin help list-nodes-ssh

Creating, Listing, and Deleting CONFIG Nodes

A CONFIG node does not support remote communication. If neither DCOM nor SSH is set up and you plan to administer your instances locally, the instances can reside on CONFIG nodes. You cannot use CONFIG nodes for instances that you plan to administer centrally.

GlassFish Server enables you to create CONFIG nodes for use by instances, obtain information about CONFIG nodes, and delete CONFIG nodes that are no longer required.

The following topics are addressed here:

- To Create a CONFIG Node
- To List CONFIG Nodes in a Domain
- To Delete a CONFIG Node

To Create a CONFIG Node

Use the create-node-config command in remote mode to create a CONFIG node.

Note: If you create an instance locally on a host for which no nodes are defined, you can create the instance without creating a node beforehand. In this situation, GlassFish Server creates a CONFIG node for you. The name of the node is the unqualified name of the host. For more information, see To Create an Instance Locally. **1.** Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the create-node-config subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the node, see the create-node-config(1) help page.

asadmin> create-node-config [--nodehost node-host] [--installdir install-dir] node-name

node-host

The name of the host that the node represents. You may omit this option. The name of the host can be determined when instances that reside on the node are created.

install-dir

The full path to the parent of the base installation directory of the GlassFish Server software on the host, for example, /export/glassfish3/. You may omit this option. The installation directory can be determined when instances that reside on the node are created.

node-name

Your choice of name for the node that you are creating.

Example 3-11 Creating a CONFIG Node

This example creates the CONFIG node cfg01. The host that the node represents and the installation directory of the GlassFish Server software on the host are to be determined when instances are added to the node.

```
asadmin> create-node-config cfg01
Command create-node-config executed successfully.
```

See Also

create-node-config(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-node-config at the command line.

Next Steps

After creating a node, you can create instances on the node as explained in To Create an Instance Locally.

To List CONFIG Nodes in a Domain

Use the list-nodes-config subcommand in remote mode to obtain information about existing CONFIG nodes in a domain.

Note: To obtain information about all existing nodes in a domain, use the list-nodes subcommand.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the list-nodes-config subcommand.

```
asadmin> list-nodes-config
```

Example 3-12 Listing Basic Information About All CONFIG Nodes in a Domain

This example lists the name, type, and host of all CONFIG nodes in the current domain.

```
asadmin> list-nodes-config
localhost-domain1 CONFIG localhost
cfg01 CONFIG cfg01.example.com
cfg02 CONFIG cfg02.example.com
Command list-nodes-config executed successfully.
```

Example 3-13 Listing Detailed Information About All CONFIG Nodes in a Domain

This example lists detailed information about all CONFIG nodes in the current domain.

```
asadmin> list-nodes-config --long=true
NODE NAME TYPE NODE HOST INSTALL DIRECTORY REFERENCED
BY
localhost-domain1 CONFIG localhost /export/glassfish3 cfg01 CONFIG cfg01.example.com /export/glassfish3 yml-i1 cfg02 CONFIG cfg02.example.com /export/glassfish3 yml-i2
Command list-nodes-config executed successfully.
```

See Also

- list-nodes(1)
- list-nodes-config(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help list-nodes
- asadmin help list-nodes-config

To Delete a CONFIG Node

Use the delete-node-config subcommand in remote mode to delete a CONFIG node.

Deleting a node removes the node from the configuration of the DAS. The node's directories and files are deleted when the last GlassFish Server instance that resides on the node is deleted.

Before You Begin

Ensure that no GlassFish Server instances reside on the node that you are deleting. For information about how to delete an instance that resides on a CONFIG node, see To Delete an Instance Locally.

- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- **2.** Confirm that no instances reside on the node that you are deleting.

```
asadmin> list-nodes-config --long=true
```

3. Run the delete-node-config subcommand.

```
asadmin> delete-node-config node-name
```

node-name

The name of the node that you are deleting.

Example 3-14 Deleting a CONFIG Node

This example confirms that no instances reside on the CONFIG node cfg01 and deletes the node cfq01.

asadmin> list-nodes	s-config -	long=true		
NODE NAME	TYPE	NODE HOST	INSTALL DIRECTORY	REFERENCED
BY				
localhost-domain1	CONFIG	localhost	/export/glassfish3	
cfg01	CONFIG	cfg01.example.com	/export/glassfish3	
cfg02	CONFIG	cfg02.example.com	/export/glassfish3	yml-i2
Command list-nodes-	-config ex	ecuted successfully.		
asadmin> delete-nod	le-config	cfg01		
Command delete-node	e-confia e	executed successfully		

See Also

- To Delete an Instance Locally
- delete-node-config(1)
- list-nodes-config(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-node-config
- asadmin help list-nodes-config

Updating and Changing the Type of a Node

GlassFish Server enables you to update the configuration data of any node and to change the type of a node.

The following topics are addressed here:

- To Update a DCOM Node
- To Update an SSH Node
- To Update a CONFIG Node
- To Change the Type of a Node

To Update a DCOM Node

Use the update-node-dcom subcommand in remote mode to update a DCOM node.

Options of this subcommand specify the new values of the node's configuration data. If you omit an option, the existing value is unchanged.

Before You Begin

Ensure that the following prerequisites are met:

- DCOM is configured on the host where the DAS is running and on the host that the node represents.
- The node that you are updating exists.
- **1.** Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the update-node-dcom subcommand.

asadmin> update-node-dcom options node-name

options

Options of the update-node-dcom subcommand for changing the node's configuration data. For information about these options, see the update-node-dcom(1) help page.

node-name

The name of the DCOM node to update.

Example 3–15 Updating a DCOM Node

This example updates the host that the node wpmdl1 represents to wj01.

```
asadmin> update-node-dcom --nodehost wj01 wpmdl1
Command update-node-dcom executed successfully.
```

See Also

update-node-dcom(1)

You can also view the full syntax and options of the subcommand by typing asadmin help update-node-dcom at the command line.

To Update an ssн Node

Use the update-node-ssh subcommand in remote mode to update an SSH node.

Options of this subcommand specify the new values of the node's configuration data. If you omit an option, the existing value is unchanged.

Before You Begin

Ensure that the following prerequisites are met:

- SSH is configured on the host where the DAS is running and on the host that the node represents.
- The node that you are updating exists.
- Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the update-node-ssh subcommand.

```
asadmin> update-node-ssh options node-name
```

options

Options of the update-node-ssh subcommand for changing the node's configuration data. For information about these options, see the update-node-ssh(1) help page.

node-name

The name of the SSH node to update.

Example 3-16 Updating an SSH Node

This example updates the host that the node sj01 represents to adc01.example.com.

```
asadmin> update-node-ssh --nodehost adc01.example.com sj01
Command update-node-ssh executed successfully.
```

See Also

update-node-ssh(1)

You can also view the full syntax and options of the subcommand by typing asadmin help update-node-ssh at the command line.

To Update a CONFIG Node

Use the update-node-config subcommand in remote mode to update a CONFIG node.

Options of this subcommand specify the new values of the node's configuration data. If you omit an option, the existing value is unchanged.

Before You Begin

Ensure that the node that you are updating exists.

- **1.** Ensure that the DAS is running. Remote subcommands require a running server.
- **2.** Run the update-node-config subcommand.

```
asadmin> uupdate-node-config options node-name
```

options

Options of the update-node-config subcommand for changing the node's configuration data. For information about these options, see the update-node-config(1) help page.

node-name

The name of the CONFIG node to update.

Example 3-17 Updating a CONFIG Node

This example updates the host that the node cfg02 represents to adc02.example.com.

```
asadmin> update-node-config --nodehost adc02.example.com cfg02
Command update-node-config executed successfully.
```

See Also

update-node-config(1)

You can also view the full syntax and options of the subcommand by typing asadmin help update-node-config at the command line.

To Change the Type of a Node

The subcommands for updating a node can also be used to change the type of a node.

Changing the type of a CONFIG node enables remote communication for the node. The type of the node after the change determines the protocol over which the node is enabled for remote communication:

- A DCOM node is enabled for communication over DCOM.
- An SSH node is enabled for communication over SSH.

As part of the process of changing the type of a node, you can also change other configuration data for the node.

Options of the subcommands for updating a node specify the new values of the node's configuration data. For most options, if you omit the option, the existing value is unchanged. However, default values are applied in the following situations:

- Any of the following options of the update-node-dcom subcommand is omitted:
 - --windowsuser
 - --windowsdomain
- Any of the following options of the update-node-ssh subcommand is omitted:
 - --sshport
 - --sshuser
 - --sshkeyfile

Caution: Changing a DCOM node or an SSH node to a CONFIG node disables remote communication for the node.

Before You Begin

Ensure that the following prerequisites are met:

- SSH or DCOM is configured on the host where the DAS is running and on the host that the node represents.
- The node the type of which you are changing exists.
- Ensure that the DAS is running.

Remote subcommands require a running server.

- Run the appropriate subcommand for updating a node, depending on the type of the node **after** the change.
 - To change the type of a node to DCOM, run the update-node-dcom subcommand on the node.

```
asadmin> update-node-dcom [options] config-or-ssh-node-name
```

options

Options of the update-node-dcom subcommand for changing the node's configuration data. For information about these options, see the update-node-dcom(1) help page.

config-or-ssh-node-name

The name of the CONFIG node or the SSH node to change.

To change the type of a node to SSH, run the update-node-ssh subcommand on the node.

asadmin> update-node-ssh [options] config-or-dcom-node-name

options

Options of the update-node-ssh subcommand for changing the node's configuration data. For information about these options, see the update-node-ssh(1) help page.

config-or-dcom-node-name

The name of the CONFIG node or the DCOM node to change.

To change the type of a node to CONFIG, run the update-node-config subcommand on the node.

asadmin> update-node-config [options] dcom-or-ssh-node-name

options

Options of the update-node-config subcommand for changing the node's configuration data. For information about these options, see the update-node-config(1) help page.

dcom-or-ssh-node-name

The name of the DCOM node or the SSH node to change.

Example 3–18 Changing a CONFIG Node to an SSH Node

This example changes the CONFIG node cfg02 to an SSH node.

```
asadmin> update-node-ssh cfg02
```

Command update-node-ssh executed successfully.

See Also

- update-node-config(1)
- update-node-dcom(1)
- update-node-ssh(1)

You can also view the full syntax and options of the subcommand by typing the following commands at the command line.

- asadmin help update-node-config
- asadmin help update-node-dcom
- asadmin help update-node-ssh

	Updating	and	Changing	the	Type	of	а	Node
--	----------	-----	----------	-----	------	----	---	------

Administering GlassFish Server Clusters

A cluster is a collection of GlassFish Server instances that work together as one logical entity. A cluster provides a runtime environment for one or more Java Platform, Enterprise Edition (Java EE) applications. A cluster provides high availability through failure protection, scalability, and load balancing.

The Group Management Service (GMS) enables instances to participate in a cluster by detecting changes in cluster membership and notifying instances of the changes. To ensure that GMS can detect changes in cluster membership, a cluster's GMS settings must be configured correctly.

The following topics are addressed here:

- About GlassFish Server Clusters
- Group Management Service
- Creating, Listing, and Deleting Clusters

About GlassFish Server Clusters

A cluster is a named collection of GlassFish Server instances that share the same applications, resources, and configuration information. For information about GlassFish Server instances, see Administering GlassFish Server Instances.

GlassFish Server enables you to administer all the instances in a cluster as a single unit from a single host, regardless of whether the instances reside on the same host or different hosts. You can perform the same operations on a cluster that you can perform on an unclustered instance, for example, deploying applications and creating resources.

A cluster provides high availability through failure protection, scalability, and load balancing.

Failure protection. If an instance or a host in a cluster fails, GlassFish Server detects the failure and recovers the user session state. If a load balancer is configured for the cluster, the load balancer redirects requests from the failed instance to other instances in the cluster. Because the same applications and resources are on all instances in the cluster, an instance can fail over to any other instance in the cluster.

To enable the user session state to be recovered, each instance in a cluster sends in-memory state data to another instance. As state data is updated in any instance, the data is replicated.

- **Scalability.** If increased capacity is required, you can add instances to a cluster with no disruption in service. When an instance is added or removed, the changes are handled automatically.
- Load balancing. If instances in a cluster are distributed among different hosts, the workload can be distributed among the hosts to increase overall system throughput.

Group Management Service

The Group Management Service (GMS) is an infrastructure component that is enabled for the instances in a cluster. When GMS is enabled, if a clustered instance fails, the cluster and the Domain Administration Server (DAS) are aware of the failure and can take action when failure occurs. Many features of GlassFish Server depend upon GMS. For example, GMS is used by the in-memory session replication, transaction service, and timer service features.

GMS is a core service of the Shoal framework. For more information about Shoal, visit the Project Shoal home page (https://shoal.dev.java.net/).

The following topics are addressed here:

- **Protocols and Transports for GMS**
- GMS Configuration Settings
- **Dotted Names for GMS Settings**
- To Preconfigure Nondefault GMS Configuration Settings
- To Change GMS Settings After Cluster Creation
- To Check the Health of Instances in a Cluster
- To Validate That Multicast Transport Is Available for a Cluster
- Discovering a Cluster When Multicast Transport Is Unavailable
- Using the Multi-Homing Feature With GMS

Protocols and Transports for GMS

You can specify that GMS should use one of the following combinations of protocol and transport for broadcasting messages:

- User Datagram Protocol (UDP) multicast
- Transmission Control Protocol (TCP) without multicast

Even if GMS should use UDP multicast for broadcasting messages, you must ensure that TCP is enabled. On Windows systems, enabling TCP involves enabling a protocol and port for security when a firewall is enabled.

If GMS should use UDP multicast for broadcasting messages and if GlassFish Server instances in a cluster are located on different hosts, the following conditions must be met:

- The DAS host and all hosts for the instances must be on the same subnet.
- UDP multicast must be enabled for the network. To test whether multicast is enabled, use the validate-multicast(1) subcommand.

If GMS should use TCP without multicast, you must configure GMS to locate the instances to use for discovering the cluster. For more information, see Discovering a Cluster When Multicast Transport Is Unavailable.

Note: If you do not configure GMS to locate the instances to use for discovering a cluster, GMS uses UDP multicast by default.

GMS Configuration Settings

GlassFish Server has the following types of GMS settings:

- GMS cluster settings These are determined during cluster creation. For more information about these settings, see To Create a Cluster.
- GMS configuration settings These are determined during configuration creation and are explained here.

The following GMS configuration settings are used in GMS for group discovery and failure detection:

group-discovery-timeout-in-millis

Indicates the amount of time (in milliseconds) an instance's GMS module will wait during instance startup for discovering other members of the group.

The group-discovery-timeout-in-millis timeout value should be set to the default or higher. The default is 5000.

max-missed-heartbeats

Indicates the maximum number of missed heartbeats that the health monitor counts before the instance can be marked as a suspected failure. GMS also tries to make a peer-to-peer connection with the suspected member. If the maximum number of missed heartbeats is exceeded and peer-to-peer connection fails, the member is marked as a suspected failure. The default is 3.

heartbeat-frequency-in-millis

Indicates the frequency (in milliseconds) at which a heartbeat is sent by each server instance to the cluster.

The failure detection interval is the max-missed-heartbeats multiplied by the heartbeat-frequency-in-millis. Therefore, the combination of defaults, 3 multiplied by 2000 milliseconds, results in a failure detection interval of 6 seconds.

Lowering the value of heartbeat-frequency-in-millis below the default would result in more frequent heartbeat messages being sent out from each member. This could potentially result in more heartbeat messages in the network than a system needs for triggering failure detection protocols. The effect of this varies depending on how quickly the deployment environment needs to have failure detection performed. That is, the (lower) number of retries with a lower heartbeat interval would make it quicker to detect failures.

However, lowering this value could result in false positives because you could potentially detect a member as failed when, in fact, the member's heartbeat is reflecting the network load from other parts of the server. Conversely, a higher timeout interval results in fewer heartbeats in the system because the time interval between heartbeats is longer. As a result, failure detection would take a longer. In addition, a startup by a failed member during this time results in a new join notification but no failure notification, because failure detection and verification were not completed.

The default is 2000.

verify-failure-waittime-in-millis

Indicates the verify suspect protocol's timeout used by the health monitor. After a member is marked as suspect based on missed heartbeats and a failed peer-to-peer connection check, the verify suspect protocol is activated and waits for the specified timeout to check for any further health state messages received in that time, and to see if a peer-to-peer connection can be made with the suspect member. If not, then the member is marked as failed and a failure notification is sent. The default is 1500.

verify-failure-connect-timeout-in-millis

Indicates the time it takes for the GMS to detect a hardware or network failure of a server instance. Be careful not to set this value too low. The smaller this timeout value is, the greater the chance of detecting false failures. That is, the instance has not failed but doesn't respond within the short window of time. The default is 10000.

The heartbeat frequency, maximum missed heartbeats, peer-to-peer connection-based failure detection, and the verify timeouts are all needed to ensure that failure detection is robust and reliable in GlassFish Server.

For the dotted names for each of these GMS configuration settings, see Dotted Names for GMS Settings. For the steps to specify these settings, see To Preconfigure Nondefault GMS Configuration Settings.

Dotted Names for GMS Settings

Below are sample get subcommands to get all the GMS configuration settings (attributes associated with the referenced mycfg configuration) and GMS cluster settings (attributes and properties associated with a cluster named mycluster).

```
asadmin> get "configs.config.mycfg.group-management-service.*"
configs.config.mycfg.group-management-service.failure-detection.heartbeat-frequenc
y-in-millis=2000
configs.config.mycfg.group-management-service.failure-detection.max-missed-heartbe
at.s=3
configs.config.mycfg.group-management-service.failure-detection.verify-failure-con
nect-timeout-in-millis=10000
configs.config.mycfg.group-management-service.failure-detection.verify-failure-wai
ttime-in-millis=1500
configs.config.mycfg.group-management-service.group-discovery-timeout-in-millis=50
asadmin> get clusters.cluster.mycluster
clusters.cluster.mycluster.config-ref=mycfg
clusters.cluster.mycluster.qms-bind-interface-address=${GMS-BIND-INTERFACE-ADDRESS}
-mvcluster}
clusters.cluster.mycluster.gms-enabled=true
clusters.cluster.mycluster.gms-multicast-address=228.9.245.47
clusters.cluster.mycluster.gms-multicast-port=9833
clusters.cluster.mycluster.name=mycluster
asadmin> get "clusters.cluster.mycluster.property.*"
clusters.cluster.mycluster.property.GMS_LISTENER_PORT=${GMS_LISTENER_
PORT-mycluster}
clusters.cluster.mycluster.property.GMS_MULTICAST_TIME_TO_LIVE=4
clusters.cluster.mycluster.property.GMS_LOOPBACK=false
clusters.cluster.mycluster.property.GMS_TCPSTARTPORT=9090
clusters.cluster.mycluster.property.GMS_TCPENDPORT=9200
```

The last get subcommand displays only the properties that have been explicitly set.

For the steps to specify these settings, see To Preconfigure Nondefault GMS Configuration Settings and To Change GMS Settings After Cluster Creation.

To Preconfigure Nondefault GMS Configuration Settings

You can preconfigure GMS with values different than the defaults without requiring a restart of the DAS and the cluster.

Create a configuration using the copy-config subcommand.

For example:

```
asadmin> copy-config default-config mycfg
```

For more information, see To Create a Named Configuration.

2. Set the values for the new configuration's GMS configuration settings.

For example:

```
asadmin> set
configs.config.mycfg.group-management-service.group-discovery-timeout-in-millis
asadmin> set
configs.config.mycfg.group-management-service.failure-detection.max-missed-hear
tbeats=5
```

For a complete list of the dotted names for these settings, see Dotted Names for GMS Settings.

3. Create the cluster so it uses the previously created configuration.

For example:

```
asadmin> create-cluster --config mycfg mycluster
```

You can also set GMS cluster settings during this step. For more information, see To Create a Cluster.

4. Create server instances for the cluster.

For example:

```
asadmin> create-instance --node localhost --cluster mycluster instance01
asadmin> create-instance --node localhost --cluster mycluster instance02
```

5. Start the cluster.

For example:

```
asadmin> start-cluster mycluster
```

See Also

You can also view the full syntax and options of a subcommand by typing asadmin help *subcommand* at the command line.

To Change GMS Settings After Cluster Creation

To avoid the need to restart the DAS and the cluster, configure GMS configuration settings before cluster creation as explained in To Preconfigure Nondefault GMS Configuration Settings.

To avoid the need to restart the DAS and the cluster, configure the GMS cluster settings during cluster creation as explained in To Create a Cluster.

Changing any GMS settings using the set subcommand after cluster creation requires a domain administration server (DAS) and cluster restart as explained here.

1. Ensure that the DAS and cluster are running.

Remote subcommands require a running server.

2. Use the get subcommand to determine the settings to change.

For example:

```
asadmin> get "configs.config.mycfg.group-management-service.*"
configs.config.mycfg.group-management-service.failure-detection.heartbeat-frequ
ency-in-millis=2000
configs.config.mycfg.group-management-service.failure-detection.max-missed-hear
configs.config.mycfg.group-management-service.failure-detection.verify-failure-
connect-timeout-in-millis=10000
configs.config.mycfg.group-management-service.failure-detection.verify-failure-
waittime-in-millis=1500
configs.config.mycfg.group-management-service.group-discovery-timeout-in-millis
```

For a complete list of the dotted names for these settings, see Dotted Names for GMS Settings.

3. Use the set subcommand to change the settings.

For example:

```
asadmin> set
configs.config.mycfg.group-management-service.group-discovery-timeout-in-millis
=6000
```

4. Use the get subcommand again to confirm that the changes were made.

For example:

```
asadmin> get
configs.config.mycfg.group-management-service.group-discovery-timeout-in-millis
```

5. Restart the DAS.

For example:

```
asadmin> stop-domain domain1
asadmin> start-domain domain1
```

6. Restart the cluster.

For example:

```
asadmin> stop-cluster mycluster
asadmin> start-cluster mycluster
```

See Also

You can also view the full syntax and options of a subcommand by typing asadmin help *subcommand* at the command line.

To Check the Health of Instances in a Cluster

The get-health subcommand only works when GMS is enabled. This is the quickest way to evaluate the health of a cluster and to detect if cluster is properly operating; that is, all members of the cluster are running and visible to DAS.

If multicast is not enabled for the network, all instances could be running (as shown by the list-instances subcommand), yet isolated from each other. The get-health subcommand does not show the instances if they are running but cannot discover each other due to multicast not being configured properly. See To Validate That Multicast Transport Is Available for a Cluster.

- Ensure that the DAS and cluster are running. Remote subcommands require a running server.
- Check whether server instances in a cluster are running by using the get-health subcommand.

Example 4–1 Checking the Health of Instances in a Cluster

This example checks the health of a cluster named cluster1.

```
asadmin> get-health cluster1
instance1 started since Wed Sep 29 16:32:46 EDT 2010
instance2 started since Wed Sep 29 16:32:45 EDT 2010
Command get-health executed successfully.
```

See Also

You can also view the full syntax and options of the subcommand by typing asadmin help get-health at the command line.

To Validate That Multicast Transport Is Available for a Cluster

Before You Begin

To test a specific multicast address, multicast port, or bind interface address, get this information beforehand using the get subcommand. Use the following subcommand to get the multicast address and port for a cluster named c1:

```
asadmin> get clusters.cluster.c1
clusters.cluster.cl.config-ref=mycfg
clusters.cluster.c1.gms-bind-interface-address=${GMS-BIND-INTERFACE-ADDRESS-c1}
clusters.cluster.cl.gms-enabled=true
clusters.cluster.cl.gms-multicast-address=228.9.174.162
clusters.cluster.cl.gms-multicast-port=5383
clusters.cluster.cl.name=c1
```

Use the following subcommand to get the bind interface address of a server instance named i1that belongs to a cluster named c1, if this system property has been set:

```
asadmin> get servers.server.i1.system-property.GMS-BIND-INTERFACE-ADDRESS-c1
servers.server.i1.system-property.GMS-BIND-INTERFACE-ADDRESS-c1.name=GMS-BIND-INTE
RFACE-ADDRESS-c1
servers.server.i1.system-property.GMS-BIND-INTERFACE-ADDRESS-c1.value=10.12.152.30
```

For information on how to set this system property, see Using the Multi-Homing Feature With GMS.

Note: Do not run the validate-multicast subcommand using the DAS and cluster's multicast address and port values while the DAS and cluster are running. Doing so results in an error.

The validate-multicast subcommand must be run at the same time on two or more machines to validate whether multicast messages are being received between the machines.

Check whether multicast transport is available for a cluster by using the validate-multicast subcommand.

Example 4–2 Validating That Multicast Transport Is Available for a Cluster

This example checks whether multicast transport is available for a cluster named c1.

Run from host sr1:

```
asadmin> validate-multicast
Will use port 2048
Will use address 228.9.3.1
Will use bind interface null
Will use wait period 2,000 (in milliseconds)
Listening for data...
Sending message with content "sr1" every 2,000 milliseconds
Received data from sr1 (loopback)
Received data from sr2
Exiting after 20 seconds. To change this timeout, use the --timeout command line
Command validate-multicast executed successfully.
```

Run from host sr2:

```
asadmin> validate-multicast
Will use port 2048
Will use address 228.9.3.1
Will use bind interface null
Will use wait period 2,000 (in milliseconds)
Listening for data...
Sending message with content "sr2" every 2,000 milliseconds
Received data from sr2 (loopback)
Received data from sr1
Exiting after 20 seconds. To change this timeout, use the --timeout command line
Command validate-multicast executed successfully.
```

Next Steps

As long as all machines see each other, multicast is validated to be working properly across the machines. If the machines are not seeing each other, set the --bindaddress option explicitly to ensure that all machines are using interface on same subnet, or increase the --timetolive option from the default of 4. If these changes fail to resolve the multicast issues, ask the network administrator to verify that the network is configured so the multicast messages can be seen between all the machines used to run the cluster.

See Also

You can also view the full syntax and options of the subcommand by typing asadmin help get-health at the command line.

Discovering a Cluster When Multicast Transport Is Unavailable

When multicast transport is unavailable, GlassFish Server instances that are joining a cluster cannot rely on broadcast messages from GMS to discover the cluster. Instead, an instance that is joining a cluster uses a running instance or the DAS in the cluster to discover the cluster.

Therefore, when multicast transport is unavailable, you must provide the locations of instances in the cluster to use for discovering the cluster. You are not required to provide the locations of all instances in the cluster. However, for an instance to discover the cluster, at least one instance whose location you provide must be running. To increase the probability of finding a running instance, provide the locations of several instances.

If the DAS will be left running after the cluster is started, provide the location of the DAS first in the list of instances. When a cluster is started, the DAS is running before any of the instances in the cluster are started.

The locations of the instances to use for discovering a cluster are part of the configuration data that you provide when creating the cluster. How to provide this data depends on how instances are distributed, as explained in the following subsections:

- To Discover a Cluster When Multiple Instances in a Cluster are Running on a Host
- To Discover a Cluster When Each Instance in a Cluster Is Running on a Different Host

To Discover a Cluster When Multiple Instances in a Cluster are Running on a Host

If multiple instances in the same cluster are running on a host, you must provide a list of uniform resource indicators (URIs). Each URI must locate a GlassFish Server instance or the DAS in the cluster.

- Ensure that the DAS is running.
 - Remote subcommands require a running server.
- 2. Create a system property to represent the port number of the port on which the DAS listens for messages from GMS for the cluster.

Use the create-system-properties subcommand for this purpose.

asadmin> create-system-properties GMS_LISTENER_PORT-cluster-name=gms-port

cluster-name

The name of the cluster to which the messages from GMS apply.

gms-port

The port number of the port on which the DAS listens for messages from GMS.

- **3.** Restart the DAS.
- When creating the cluster, set the GMS_DISCOVERY_URI_LIST property to a comma-separated list of URIs that locate instances to use for discovering the cluster.

asadmin> create-cluster --properties GMS_DISCOVERY_URI_LIST=uri-list

cluster-name

uri-list

A comma-separated list of URIs that locate a GlassFish Server instance or the DAS in the cluster.

The format of each URI in the list is as follows:

scheme: //host-name-or -IP-address:port

- *scheme* is the URI scheme, which is tcp.
- host-name-or -IP-address is the host name or IP address of the host on which the instance is running.
- port is the port number of the port on which the instance will listen for messages from GMS.

cluster-name

The name of the cluster that you are creating.

Note: For complete instructions for creating a cluster, see To Create a Cluster.

- When you add each instance to the cluster, set the system property GMS_LISTENER_ PORT-clustername for the instance.
 - To create the instance centrally, run the following command:

```
asadmin> create-instance --node node-name
--systemproperties GMS_LISTENER_PORT-cluster-name=gms-port --cluster
cluster-name instance-name
```

To create the instance locally, run the following command:

```
asadmin> create-local-instance
--systemproperties GMS_LISTENER_PORT-cluster-name=gms-port --cluster
cluster-name instance-name
```

node-name

The name of an existing GlassFish Server node on which the instance is to reside. For more information about nodes, see Administering GlassFish Server Nodes.

cluster-name

The name of the cluster to which the you are adding the instance.

gms-port

The port number of the port on which the instance listens for messages from GMS.

instance-name

The name of the instance that you are creating.

Note: For full instructions for adding an instance to a cluster, see the following sections:

- To Create an Instance Centrally
- To Create an Instance Locally

Example 4-3 Discovering a Cluster When Multiple Instances are Running on a Host

This example creates a cluster that is named topcluster for which GMS is not using multicast for broadcasting messages.

The cluster contains the instances instance101 and instance102. These instances reside on the host whose IP address is 10.152.23.224 and listen for GMS events on ports 9091 and 9092. The DAS is also running on this host and listens for GMS events on port 9090.

Instances that are joining the cluster will use the DAS and the instances instance101 and instance102 to discover the cluster.

```
asadmin> create-system-properties GMS_LISTENER_PORT-tcpcluster=9090
Command create-system-properties executed successfully.
asadmin> restart-domain
Successfully restarted the domain
Command restart-domain executed successfully.
asadmin> create-cluster --properties GMS_DISCOVERY_URI_LIST=
tcp'\\:'//10.152.23.224'\\:'9090,
tcp'\\:'//10.152.23.224'\\:'9091,
tcp'\\:'//10.152.23.224'\\:'9092 tcpcluster
Command create-cluster executed successfully.
asadmin> create-local-instance
--systemproperties GMS_LISTENER_PORT-tcpcluster=9091 --cluster tcpcluster
instance101
Rendezvoused with DAS on localhost: 4848.
Port Assignments for server instance instance101:
JMX_SYSTEM_CONNECTOR_PORT=28686
JMS_PROVIDER_PORT=27676
HTTP_LISTENER_PORT=28080
ASADMIN_LISTENER_PORT=24848
JAVA_DEBUGGER_PORT=29009
IIOP_SSL_LISTENER_PORT=23820
IIOP_LISTENER_PORT=23700
OSGI_SHELL_TELNET_PORT=26666
HTTP_SSL_LISTENER_PORT=28181
IIOP_SSL_MUTUALAUTH_PORT=23920
Command create-local-instance executed successfully.
asadmin> create-local-instance
--systemproperties GMS_LISTENER_PORT-tcpcluster=9092 --cluster tcpcluster
instance102
Rendezvoused with DAS on localhost:4848.
Using DAS host localhost and port 4848 from existing das.properties for node
localhost-domain1. To use a different DAS, create a new node using
create-node-ssh or create-node-config. Create the instance with the new node and
correct host and port:
asadmin --host das_host --port das_port create-local-instance --node node_name
instance_name.
Port Assignments for server instance instance102:
JMX_SYSTEM_CONNECTOR_PORT=28687
JMS_PROVIDER_PORT=27677
HTTP_LISTENER_PORT=28081
ASADMIN_LISTENER_PORT=24849
JAVA_DEBUGGER_PORT=29010
IIOP_SSL_LISTENER_PORT=23821
IIOP_LISTENER_PORT=23701
OSGI_SHELL_TELNET_PORT=26667
HTTP_SSL_LISTENER_PORT=28182
IIOP_SSL_MUTUALAUTH_PORT=23921
Command create-local-instance executed successfully.
```

See Also

- create-system-properties(1)
- To Create a Cluster
- To Create an Instance Centrally
- To Create an Instance Locally

To Discover a Cluster When Each Instance in a Cluster Is Running on a Different Host

If all instances in a cluster and the DAS are running on different hosts, you can specify the locations of instances to use for discovering the cluster as follows:

- By specifying a list of host names or Internet Protocol (IP) addresses. Each host name or IP address must locate a host on which the DAS or a GlassFish Server instance in the cluster is running. Instances that are joining the cluster will use the DAS or the instances to discover the cluster.
- By generating the list of locations automatically. The generated list contains the locations of the DAS and all instances in the cluster.

Multiple instances on the same host cannot be members of the same cluster.

- 1. Ensure that the DAS is running.
 - Remote subcommands require a running server.
- **2.** When creating the cluster, set the properties of the cluster as follows:
 - Set the GMS_DISCOVERY_URI_LIST property to one of the following values:
 - A comma-separated list of IP addresses or host names on which the DAS or the instances to use for discovering the cluster are running.
 - The list can contain a mixture of IP addresses and host names.
 - The keyword generate.
 - Set the GMS_LISTENER_PORT property to a port number that is unique for the cluster in the domain.

If you are specifying a list of IP addresses or host names, type the following command:

```
asadmin> create-cluster --properties GMS_DISCOVERY_URI_LIST=host-list:
GMS LISTENER_PORT=gms-port cluster-name
```

If you are specifying the keyword generate, type the following command:

```
asadmin> create-cluster --properties GMS_DISCOVERY_URI_LIST=generate:
GMS_LISTENER_PORT=gms-port cluster-name
```

host-list

A comma-separated list of IP addresses or host names on which the DAS or the instances to use for discovering the cluster are running.

qms-port

The port number of the port on which the cluster listens for messages from GMS.

cluster-name

The name of the cluster that you are creating.

Note: For complete instructions for creating a cluster, see To Create a Cluster.

Example 4–4 Discovering a Cluster by Specifying a List of IP Addresses

This example creates a cluster that is named ipcluster for which GMS is not using multicast for broadcasting messages. The instances to use for discovering the cluster are located through a list of IP addresses. In this example, one instance in the cluster is running on each host and the DAS is running on a separate host. The cluster listens for messages from GMS on port 9090.

```
asadmin> create-cluster --properties 'GMS_DISCOVERY_URI_LIST=
10.152.23.225,10.152.23.226,10.152.23.227,10.152.23.228:
GMS_LISTENER_PORT=9090' ipcluster
Command create-cluster executed successfully.
```

Example 4-5 Discovering a Cluster by Generating a List of Locations of Instances

This example creates a cluster that is named gencluster for which GMS is not using multicast for broadcasting messages. The list of locations of instances to use for discovering the cluster is generated automatically. In this example, one instance in the cluster is running on each host and the DAS is running on a separate host. The cluster listens for messages from GMS on port 9090.

```
asadmin> create-cluster --properties 'GMS DISCOVERY URI LIST=generate:
GMS LISTENER PORT=9090' gencluster
Command create-cluster executed successfully.
```

Next Steps

After creating the cluster, add instances to the cluster as explained in the following sections:

- To Create an Instance Centrally
- To Create an Instance Locally

See Also

- To Create a Cluster
- To Create an Instance Centrally
- To Create an Instance Locally

Using the Multi-Homing Feature With GMS

Multi-homing enables GlassFish Server clusters to be used in an environment that uses multiple Network Interface Cards (NICs). A multi-homed host has multiple network connections, of which the connections may or may not be the on same network. Multi-homing provides the following benefits:

- Provides redundant network connections within the same subnet. Having multiple NICs ensures that one or more network connections are available for communication.
- Supports communication across two or more different subnets. The DAS and all server instances in the same cluster must be on the same subnet for GMS communication, however.

- Binds to a specific IPv4 address and receives GMS messages in a system that has multiple IP addresses configured. The responses for GMS messages received on a particular interface will also go out through that interface.
- Supports separation of external and internal traffic.

Traffic Separation Using Multi-Homing

You can separate the internal traffic resulting from GMS from the external traffic. Traffic separation enables you plan a network better and augment certain parts of the network, as required.

Consider a simple cluster, c1, with three instances, i101, i102, and i103. Each instance runs on a different machine. In order to separate the traffic, the multi-homed machine should have at least two IP addresses belonging to different networks. The first IP as the external IP and the second one as internal IP. The objective is to expose the external IP to user requests, so that all the traffic from the user requests would be through them. The internal IP is used only by the cluster instances for internal communication through GMS. The following procedure describes how to set up traffic separation.

To configure multi-homed machines for GMS without traffic separation, skip the steps or commands that configure the EXTERNAL-ADDR system property, but perform the others.

To avoid having to restart the DAS or cluster, perform the following steps in the specified order.

To set up traffic separation, follow these steps:

- 1. Create the system properties EXTERNAL-ADDR and GMS-BIND-INTERFACE-ADDRESS-c1 for the DAS.
 - asadmin create-system-properties target server EXTERNAL-ADDR=192.155.35.4
 - asadmin create-system-properties target server GMS-BIND-INTERFACE-ADDRESS-c1=10.12.152.20
- **2.** Create the cluster with the default settings.

Use the following command:

asadmin create-cluster c1

A reference to a system property for GMS traffic is already set up by default in the gms-bind-interface-address cluster setting. The default value of this setting is \${GMS-BIND-INTERFACE-ADDRESS-cluster-name}.

3. When creating the clustered instances, configure the external and GMS IP addresses.

Use the following commands:

- asadmin create-instance node localhost cluster c1 systemproperties EXTERNAL-ADDR=192.155.35.5:GMS-BIND-INTERFACE-ADDRESS-c1=10.12.152. 30 i101
- asadmin create-instance node localhost cluster c1 systemproperties EXTERNAL-ADDR=192.155.35.6:GMS-BIND-INTERFACE-ADDRESS-c1=10.12.152. 40 i102
- asadmin create-instance node localhost cluster c1 systemproperties EXTERNAL-ADDR=192.155.35.7:GMS-BIND-INTERFACE-ADDRESS-c1=10.12.152. 50 i103

4. Set the address attribute of HTTP listeners to refer to the EXTERNAL-ADDR system properties.

Use the following commands:

```
asadmin set
c1-config.network-config.network-listeners.network-listener.http-1.address=\${E
XTERNAL-ADDR }
asadmin set
c1-config.network-config.network-listeners.network-listener.http-2.address=\${E
XTERNAL-ADDR }
```

Creating, Listing, and Deleting Clusters

GlassFish Server enables you to create clusters, obtain information about clusters, and delete clusters that are no longer required.

The following topics are addressed here:

- To Create a Cluster
- To List All Clusters in a Domain
- To Delete a Cluster

To Create a Cluster

Use the create-cluster subcommand in remote mode to create a cluster.

To ensure that the GMS can detect changes in cluster membership, a cluster's GMS settings must be configured correctly. To avoid the need to restart the DAS and the cluster, configure a cluster's GMS settings when you create the cluster. If you change GMS settings for an existing cluster, the DAS and the cluster must be restarted to apply the changes.

When you create a cluster, GlassFish Server automatically creates a Message Queue cluster for the GlassFish Server cluster. For more information about Message Queue clusters, see Using Message Queue Broker Clusters With GlassFish Server.

Before You Begin

If the cluster is to reference an existing named configuration, ensure that the configuration exists. For more information, see To Create a Named Configuration. If you are using a named configuration to preconfigure GMS settings, ensure that these settings have the required values in the named configuration. For more information, see To Preconfigure Nondefault GMS Configuration Settings.

If you are configuring the cluster's GMS settings when you create the cluster, ensure that you have the following information:

- The address on which GMS listens for group events
- The port number of the communication port on which GMS listens for group events
- The maximum number of iterations or transmissions that a multicast message for GMS events can experience before the message is discarded
- The lowest port number in the range of ports from which GMS selects a TCP port on which to listen

The highest port number in the range of ports from which GMS selects a TCP port on which to listen

If the DAS is running on a multihome host, ensure that you have the Internet Protocol (IP) address of the network interface on the DAS host to which GMS binds.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the create-cluster subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the cluster, see the create-cluster(1) help page.

If multicast transport is available, run the create-cluster subcommand as follows:

```
asadmin> create-cluster --config configuration
--multicastaddress multicast-address --multicastport multicast-port
--properties GMS MULTICAST TIME TO LIVE=max-iterations:
GMS_TCPSTARTPORT=start-port:GMS_TCPENDPORT=end-port cluster-name
```

If multicast transport is **not** available, run the create-cluster subcommand as follows:

```
asadmin> create-cluster --config configuration
--properties GMS_DISCOVERY_URI_LIST=discovery-instances:
GMS_LISTENER_PORT=gms-port
cluster-name
```

configuration

An existing named configuration that the cluster is to reference.

multicast-address

The address on which GMS listens for group events.

multicast-port

The port number of the communication port on which GMS listens for group events.

max-iterations

The maximum number of iterations or transmissions that a multicast message for GMS events can experience before the message is discarded.

discovery-instances

Instances to use for discovering the cluster. For more information, see Discovering a Cluster When Multicast Transport Is Unavailable.

gms-port

The port number of the port on which the cluster listens for messages from GMS.

start-port

The lowest port number in the range of ports from which GMS selects a TCP port on which to listen. The default is 9090.

end-port

The highest port number in the range of ports from which GMS selects a TCP port on which to listen. The default is 9200.

cluster-name

Your choice of name for the cluster that you are creating.

If necessary, create a system property to represent the IP address of the network interface on the DAS host to which GMS binds.

This step is necessary only if the DAS is running on a multihome host.

```
asadmin> create-system-properties
GMS-BIND-INTERFACE-ADDRESS-cluster-name=das-bind-address
```

cluster-name

The name that you assigned to the cluster in Step 2.

das-bind-address

The IP address of the network interface on the DAS host to which GMS binds.

Example 4-6 Creating a Cluster for a Network in Which Multicast Transport Is Available

This example creates a cluster that is named ltscluster for which port 1169 is to be used for secure IIOP connections. Because the --config option is not specified, the cluster references a copy of the named configuration default-config that is named 1tscluster-config. This example assumes that multicast transport is available.

```
asadmin> create-cluster
--systemproperties IIOP_SSL_LISTENER_PORT=1169
ltscluster
Command create-cluster executed successfully.
```

Example 4-7 Creating a Cluster and Setting GMS Options for a Network in Which Multicast Transport Is Available

This example creates a cluster that is named pmdcluster, which references the existing configuration clusterpresets and for which the cluster's GMS settings are configured as follows:

- GMS listens for group events on address 228.9.3.1 and port 2048.
- A multicast message for GMS events is discarded after 3 iterations or transmissions.
- GMS selects a TCP port on which to listen from ports in the range 10000-10100.

This example assumes that multicast transport is available.

```
asadmin> create-cluster --config clusterpresets
--multicastaddress 228.9.3.1 --multicastport 2048
--properties GMS_MULTICAST_TIME_TO_LIVE=3:
GMS_TCPSTARTPORT=10000:GMS_TCPENDPORT=10100 pmdcluster
Command create-cluster executed successfully.
```

Next Steps

After creating a cluster, you can add GlassFish Server instances to the cluster as explained in the following sections:

- To Create an Instance Centrally
- To Create an Instance Locally

See Also

- To Create a Named Configuration
- To Preconfigure Nondefault GMS Configuration Settings
- Using Message Queue Broker Clusters With GlassFish Server
- create-cluster(1)
- create-system-properties(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help create-cluster
- asadmin help create-system-properties

To List All Clusters in a Domain

Use the list-clusters subcommand in remote mode to obtain information about existing clusters in a domain.

- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- **2.** Run the list-clusters subcommand.

```
asadmin> list-clusters
```

Example 4-8 Listing All Clusters in a Domain

This example lists all clusters in the current domain.

```
asadmin> list-clusters
pmdclust not running
ymlclust not running
Command list-clusters executed successfully.
```

Example 4-9 Listing All Clusters That Are Associated With a Node

This example lists the clusters that contain an instance that resides on the node sj01.

```
asadmin> list-clusters sj01
ymlclust not running
Command list-clusters executed successfully.
```

See Also

```
list-clusters(1)
```

You can also view the full syntax and options of the subcommand by typing asadmin help list-clusters at the command line.

To Delete a Cluster

Use the delete-cluster subcommand in remote mode to remove a cluster from the DAS configuration.

If the cluster's named configuration was created automatically for the cluster and no other clusters or unclustered instances refer to the configuration, the configuration is deleted when the cluster is deleted.

Before You Begin

Ensure that following prerequisites are met:

- The cluster that you are deleting is stopped. For information about how to stop a cluster, see To Stop a Cluster.
- The cluster that you are deleting contains no GlassFish Server instances. For information about how to remove instances from a cluster, see the following sections:
 - To Delete an Instance Centrally
 - To Delete an Instance Locally
- Ensure that the DAS is running.

Remote subcommands require a running server.

2. Confirm that the cluster is stopped.

```
asadmin> list-clusters cluster-name
```

cluster-name

The name of the cluster that you are deleting.

Confirm that the cluster contains no instances.

```
asadmin> list-instances cluster-name
```

cluster-name

The name of the cluster that you are deleting.

Run the delete-cluster subcommand.

```
asadmin> delete-cluster cluster-name
```

cluster-name

The name of the cluster that you are deleting.

Example 4-10 Deleting a Cluster

This example confirms that the cluster adccluster is stopped and contains no instances and deletes the cluster adccluster.

```
asadmin> list-clusters adccluster
adccluster not running
Command list-clusters executed successfully.
asadmin> list-instances adccluster
Nothing to list.
Command list-instances executed successfully.
asadmin> delete-cluster adccluster
Command delete-cluster executed successfully.
```

See Also

- To Stop a Cluster
- To Delete an Instance Centrally
- To Delete an Instance Locally
- delete-cluster(1)
- list-clusters(1)
- list-instances(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-cluster
- asadmin help list-clusters
- asadmin help list-instances

Administering GlassFish Server Instances

A GlassFish Server instance is a single Virtual Machine for the Java platform (Java Virtual Machine or JVM machine) on a single node in which GlassFish Server is running. A node defines the host where the GlassFish Server instance resides. The JVM machine must be compatible with the Java Platform, Enterprise Edition (Java EE).

GlassFish Server instances form the basis of an application deployment. An instance is a building block in the clustering, load balancing, and session persistence features of GlassFish Server. Each instance belongs to a single domain and has its own directory structure, configuration, and deployed applications. Every instance contains a reference to a node that defines the host where the instance resides.

The following topics are addressed here:

- Types of GlassFish Server Instances
- Administering GlassFish Server Instances Centrally
- Administering GlassFish Server Instances Locally
- Resynchronizing GlassFish Server Instances and the DAS
- Migrating EJB Timers

Types of GlassFish Server Instances

Each GlassFish Server instance is one of the following types of instance:

Standalone instance

A standalone instance does not share its configuration with any other instances or clusters. A standalone instance is created if either of the following conditions is met:

- No configuration or cluster is specified in the command to create the instance.
- A configuration that is not referenced by any other instances or clusters is specified in the command to create the instance.

When no configuration or cluster is specified, a copy of the default-config configuration is created for the instance. The name of this configuration is *instance-name*-config, where *instance-name* represents the name of an unclustered server instance.

Shared instance

A shared instance shares its configuration with other instances or clusters. A shared instance is created if a configuration that is referenced by other instances or clusters is specified in the command to create the instance.

Clustered instance

A clustered instance inherits its configuration from the cluster to which the instance belongs and shares its configuration with other instances in the cluster. A clustered instance is created if a cluster is specified in the command to create the instance.

Any instance that is not part of a cluster is considered an unclustered server instance. Therefore, standalone instances and shared instances are unclustered server instances.

Administering GlassFish Server Instances Centrally

Centralized administration requires the Distributed Component Object Model (DCOM) remote protocol or secure shell (SSH) to be set up. If DCOM or SSH is set up, you can administer clustered instances without the need to log in to hosts where remote instances reside. For information about setting up DCOM and SSH, see Enabling Centralized Administration of GlassFish Server Instances.

Administering GlassFish Server instances centrally involves the following tasks:

- To Create an Instance Centrally
- To List All Instances in a Domain
- To Delete an Instance Centrally
- To Start a Cluster
- To Stop a Cluster
- To Start an Individual Instance Centrally
- To Stop an Individual Instance Centrally
- To Restart an Individual Instance Centrally

To Create an Instance Centrally

Use the create-instance subcommand in remote mode to create a GlassFish Server instance centrally. Creating an instance adds the instance to the DAS configuration and creates the instance's files on the host where the instance resides.

If the instance is a clustered instance that is managed by GMS, system properties for the instance that relate to GMS must be configured correctly. To avoid the need to restart the DAS and the instance, configure an instance's system properties that relate to GMS when you create the instance. If you change GMS-related system properties for an existing instance, the DAS and the instance must be restarted to apply the changes. For information about GMS, see Group Management Service.

Before You Begin

Ensure that following prerequisites are met:

- The node where the instance is to reside exists.
- The node where the instance is to reside is either enabled for remote communication or represents the host on which the DAS is running. For information about how to create a node that is enabled for remote communication, see the following sections:
 - To Create a DCOM Node
 - To Create an SSH Node
- The user of the DAS can use DCOM or SSH to log in to the host for the node where the instance is to reside.

If any of these prerequisites is not met, create the instance locally as explained in To Create an Instance Locally.

If you are adding the instance to a cluster, ensure that the cluster to which you are adding the instance exists. For information about how to create a cluster, see To Create a Cluster.

If the instance is to reference an existing named configuration, ensure that the configuration exists. For more information, see To Create a Named Configuration.

The instance might be a clustered instance that is managed by GMS and resides on a node that represents a multihome host. In this situation, ensure that you have the Internet Protocol (IP) address of the network interface to which GMS binds.

- Ensure that the DAS is running. Remote subcommands require a running server.
- **2.** Run the create-instance subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the instance, see the create-instance(1) help page.

If you are creating a standalone instance, do not specify a cluster.

If the instance is to reference an existing configuration, specify a configuration that no other cluster or instance references.

```
asadmin> create-instance --node node-name
[--config configuration-name]instance-name
```

node-name

The node on which the instance is to reside.

configuration-name

The name of the existing named configuration that the instance will reference.

If you do not require the instance to reference an existing configuration, omit this option. A copy of the default-config configuration is created for the instance. The name of this configuration is *instance-name*-config, where *instance-name* is the name of the server instance.

instance-name

Your choice of name for the instance that you are creating.

If you are creating a shared instance, specify the configuration that the instance will share with other clusters or instances.

Do *not* specify a cluster.

```
asadmin> create-instance --node node-name
--config configuration-name instance-name
```

node-name

The node on which the instance is to reside.

configuration-name

The name of the existing named configuration that the instance will reference.

instance-name

Your choice of name for the instance that you are creating.

If you are creating a clustered instance, specify the cluster to which the instance will belong.

If the instance is managed by GMS and resides on a node that represents a multihome host, specify the GMS-BIND-INTERFACE-ADDRESS-cluster-name system property.

```
asadmin> create-instance --cluster cluster-name --node node-name
[--systemproperties
{\tt GMS-BIND-INTERFACE-ADDRESS-} cluster-name=bind-address]\ instance-name
```

cluster-name

The name of the cluster to which you are adding the instance.

node-name

The node on which the instance is to reside.

bind-address

The IP address of the network interface to which GMS binds. Specify this option only if the instance is managed by GMS and resides on a node that represents a multihome host.

instance-name

Your choice of name for the instance that you are creating.

Example 5-1 Creating a Clustered Instance Centrally

This example adds the instance pmd-i1 to the cluster pmdclust in the domain domain1. The instance resides on the node sj01, which represents the host sj01.example.com.

```
asadmin> create-instance --cluster pmdclust --node sj01 pmd-i1
Port Assignments for server instance pmd-i1:
JMX_SYSTEM_CONNECTOR_PORT=28686
JMS_PROVIDER_PORT=27676
HTTP_LISTENER_PORT=28080
ASADMIN LISTENER PORT=24848
IIOP SSL LISTENER PORT=23820
IIOP_LISTENER_PORT=23700
HTTP_SSL_LISTENER_PORT=28181
IIOP_SSL_MUTUALAUTH_PORT=23920
The instance, pmd-i1, was created on host sj01.example.com
Command create-instance executed successfully.
```

See Also

- To Create a DCOM Node
- To Create an SSH Node
- To Create an Instance Locally
- create-instance(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-instance at the command line.

Next Steps

After creating an instance, you can start the instance as explained in the following sections:

- To Start an Individual Instance Centrally
- To Stop an Individual Instance Locally

To List All Instances in a Domain

Use the list-instances subcommand in remote mode to obtain information about existing instances in a domain.

- **1.** Ensure that the DAS is running. Remote subcommands require a running server.
- Run the list-instances subcommand.

```
asadmin> list-instances
```

Example 5–2 Listing Basic Information About All GlassFish Server Instances in a

This example lists the name and status of all GlassFish Server instances in the current domain.

```
asadmin> list-instances
pmd-i2 running
yml-i2 running
pmd-i1 running
yml-i1 running
pmdsal not running
Command list-instances executed successfully.
```

Example 5-3 Listing Detailed Information About All GlassFish Server Instances in a Domain

This example lists detailed information about all GlassFish Server instances in the current domain.

```
asadmin> list-instances --long=true
NAME HOST PORT PID CLUSTER STATE
pmd-i1 sj01.example.com 24848 31310 pmdcluster running
yml-i1 sj01.example.com 24849 25355 ymlcluster running
pmdsal localhost 24848 -1 --- not running
pmd-i2 sj02.example.com 24848 22498 pmdcluster running
yml-i2 sj02.example.com 24849 20476 ymlcluster running
ymlsal localhost 24849 -1 --- not running
Command list-instances executed successfully.
```

See Also

```
list-instances(1)
```

You can also view the full syntax and options of the subcommand by typing asadmin help list-instances at the command line.

To Delete an Instance Centrally

Use the delete-instance subcommand in remote mode to delete a GlassFish Server instance centrally.

Caution: If you are using a Java Message Service (JMS) cluster with a master broker, do not delete the instance that is associated with the master broker. If this instance must be deleted, use the change-master-broker subcommand to assign the master broker to a different instance.

Deleting an instance involves the following:

- Removing the instance from the configuration of the DAS
- Deleting the instance's files from file system

Before You Begin

Ensure that the instance that you are deleting is not running. For information about how to stop an instance, see the following sections:

- To Stop an Individual Instance Centrally
- To Stop an Individual Instance Locally
- Ensure that the DAS is running. Remote subcommands require a running server.
- Confirm that the instance is not running.

```
asadmin> list-instances instance-name
```

instance-name

The name of the instance that you are deleting.

3. Run the delete-instance subcommand.

```
asadmin> delete-instance instance-name
```

instance-name

The name of the instance that you are deleting.

Example 5-4 Deleting an Instance Centrally

This example confirms that the instance pmd-i1 is not running and deletes the instance.

```
asadmin> list-instances pmd-i1
pmd-i1 not running
Command list-instances executed successfully.
asadmin> delete-instance pmd-i1
Command _delete-instance-filesystem executed successfully.
The instance, pmd-i1, was deleted from host sj01.example.com
Command delete-instance executed successfully.
```

See Also

To Stop an Individual Instance Centrally

- To Stop an Individual Instance Locally
- change-master-broker(1)
- delete-instance(1)
- list-instances(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-instance
- asadmin help list-instances

To Start a Cluster

Use the start-cluster subcommand in remote mode to start a cluster.

Starting a cluster starts all instances in the cluster that are not already running.

Before You Begin

Ensure that following prerequisites are met:

- Each node where an instance in the cluster resides is either enabled for remote communication or represents the host on which the DAS is running.
- The user of the DAS can use DCOM or SSH to log in to the host for any node where instances in the cluster reside.

If any of these prerequisites is not met, start the cluster by starting each instance locally as explained in To Start an Individual Instance Locally.

Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the start-cluster subcommand.

```
asadmin> start-cluster cluster-name
```

cluster-name

The name of the cluster that you are starting.

Example 5-5 Starting a Cluster

This example starts the cluster pmdcluster.

```
asadmin> start-cluster pmdcluster
Command start-cluster executed successfully.
```

See Also

- To Start an Individual Instance Locally
- start-cluster(1)

You can also view the full syntax and options of the subcommand by typing asadmin help start-cluster at the command line.

Next Steps

After starting a cluster, you can deploy applications to the cluster. For more information, see GlassFish Server Open Source Edition Application Deployment Guide.

To Stop a Cluster

Use the stop-cluster subcommand in remote mode to stop a cluster.

Stopping a cluster stops all running instances in the cluster.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the stop-cluster subcommand.

```
asadmin> stop-cluster cluster-name
```

cluster-name

The name of the cluster that you are stopping.

Example 5-6 Stopping a Cluster

This example stops the cluster pmdcluster.

```
asadmin> stop-cluster pmdcluster
```

Command stop-cluster executed successfully.

See Also

stop-cluster(1)

You can also view the full syntax and options of the subcommand by typing asadmin help stop-cluster at the command line.

Troubleshooting

If instances in the cluster have become unresponsive and fail to stop, run the subcommand again with the --kill option set to true. When this option is true, the subcommand uses functionality of the operating system to kill the process for each running instance in the cluster.

To Start an Individual Instance Centrally

Use the start-instance subcommand in remote mode to start an individual instance centrally.

Before You Begin

Ensure that following prerequisites are met:

- The node where the instance resides is either enabled for remote communication or represents the host on which the DAS is running.
- The user of the DAS can use DCOM or SSH to log in to the host for the node where the instance resides.

If any of these prerequisites is not met, start the instance locally as explained in To Start an Individual Instance Locally.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the start-instance subcommand.

asadmin> start-instance instance-name

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for controlling the behavior of the instance, see the start-instance(1) help page.

instance-name

The name of the instance that you are starting.

Example 5–7 Starting an Individual Instance Centrally

This example starts the instance pmd-i2, which resides on the node sj02. This node represents the host sj02.example.com. The configuration of the instance on this node already matched the configuration of the instance in the DAS when the instance was started.

```
asadmin> start-instance pmd-i2
CLI801 Instance is already synchronized
Waiting for pmd-i2 to start .....
Successfully started the instance: pmd-i2
instance Location: /export/glassfish3/glassfish/nodes/sj02/pmd-i2
Log File: /export/glassfish3/glassfish/nodes/sj02/pmd-i2/logs/server.log
Admin Port: 24851
Command start-local-instance executed successfully.
The instance, pmd-i2, was started on host sj02.example.com
Command start-instance executed successfully.
```

See Also

```
start-instance(1)
```

You can also view the full syntax and options of the subcommand by typing asadmin help start-instance at the command line.

Next Steps

After starting an instance, you can deploy applications to the instance. For more information, see the GlassFish Server Open Source Edition Application Deployment Guide.

To Stop an Individual Instance Centrally

Use the stop-instance subcommand in remote mode to stop an individual instance centrally.

When an instance is stopped, the instance stops accepting new requests and waits for all outstanding requests to be completed.

- **1.** Ensure that the DAS is running. Remote subcommands require a running server.
- Run the stop-instance subcommand.

Example 5–8 Stopping an Individual Instance Centrally

This example stops the instance pmd-i2.

```
asadmin> stop-instance pmd-i2
The instance, pmd-i2, is stopped.
Command stop-instance executed successfully.
```

See Also

```
stop-instance(1)
```

You can also view the full syntax and options of the subcommand by typing asadmin help stop-instance at the command line.

Troubleshooting

If the instance has become unresponsive and fails to stop, run the subcommand again with the --kill option set to true. When this option is true, the subcommand uses functionality of the operating system to kill the instance process.

To Restart an Individual Instance Centrally

Use the restart-instance subcommand in remote mode to start an individual instance centrally.

When this subcommand restarts an instance, the DAS synchronizes the instance with changes since the last synchronization as described in Default Synchronization for Files and Directories.

If you require different synchronization behavior, stop and start the instance as explained in To Resynchronize an Instance and the DAS Online.

1. Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the restart-instance subcommand.

```
asadmin> restart-instance instance-name
```

instance-name

The name of the instance that you are restarting.

Example 5–9 Restarting an Individual Instance Centrally

This example restarts the instance pmd-i2.

```
asadmin> restart-instance pmd-i2
pmd-i2 was restarted.
Command restart-instance executed successfully.
```

See Also

- To Stop an Individual Instance Centrally
- To Start an Individual Instance Centrally
- restart-instance(1)

You can also view the full syntax and options of the subcommand by typing asadmin help restart-instance at the command line.

Troubleshooting

If the instance has become unresponsive and fails to stop, run the subcommand again with the --kill option set to true. When this option is true, the subcommand uses functionality of the operating system to kill the instance process before restarting the instance.

Administering GlassFish Server Instances Locally

Local administration does not require DCOM or SSH to be set up. If neither DCOM nor SSH is set up, you must log in to each host where remote instances reside and administer the instances individually.

Administering GlassFish Server instances locally involves the following tasks:

- To Create an Instance Locally
- To Delete an Instance Locally
- To Start an Individual Instance Locally
- To Stop an Individual Instance Locally
- To Restart an Individual Instance Locally

Note: Even if neither DCOM nor SSH is set up, you can obtain information about instances in a domain without logging in to each host where remote instances reside. For instructions, see To List All Instances in a Domain.

To Create an Instance Locally

Use the create-local-instance subcommand in remote mode to create a GlassFish Server instance locally. Creating an instance adds the instance to the DAS configuration and creates the instance's files on the host where the instance resides.

If the instance is a clustered instance that is managed by GMS, system properties for the instance that relate to GMS must be configured correctly. To avoid the need to restart the DAS and the instance, configure an instance's system properties that relate to GMS when you create the instance. If you change GMS-related system properties for an existing instance, the DAS and the instance must be restarted to apply the changes. For information about GMS, see Group Management Service.

Before You Begin

If you plan to specify the node on which the instance is to reside, ensure that the node exists.

Note: If you create the instance on a host for which no nodes are defined, you can create the instance without creating a node beforehand. In this situation, GlassFish Server creates a CONFIG node for you. The name of the node is the unqualified name of the host.

For information about how to create a node, see the following sections:

- To Create a DCOM Node
- To Create an SSH Node
- To Create a CONFIG Node

If you are adding the instance to a cluster, ensure that the cluster to which you are adding the instance exists. For information about how to create a cluster, see To Create a Cluster.

If the instance is to reference an existing named configuration, ensure that the configuration exists. For more information, see To Create a Named Configuration.

The instance might be a clustered instance that is managed by GMS and resides on a node that represents a multihome host. In this situation, ensure that you have the Internet Protocol (IP) address of the network interface to which GMS binds.

- **1.** Ensure that the DAS is running. Remote subcommands require a running server.
- **2.** Log in to the host that is represented by the node where the instance is to reside.
- **3.** Run the create-local-instance subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the instance, see the create-local-instance(1) help page.

If you are creating a standalone instance, do not specify a cluster.

If the instance is to reference an existing configuration, specify a configuration that no other cluster or instance references.

```
$ asadmin --host das-host [--port admin-port]
create-local-instance [--node node-name] [--config
configuration-name]instance-name
```

das-host

The name of the host where the DAS is running.

admin-port

The HTTP or HTTPS port on which the DAS listens for administration requests. If the DAS listens on the default port for administration requests, you may omit this option.

node-name

The node on which the instance is to reside.

If you are creating the instance on a host for which fewer than two nodes are defined, you may omit this option.

If no nodes are defined for the host, GlassFish Server creates a CONFIG node for you. The name of the node is the unqualified name of the host.

If one node is defined for the host, the instance is created on that node.

configuration-name

The name of the existing named configuration that the instance will reference.

If you do not require the instance to reference an existing configuration, omit this option. A copy of the default-config configuration is created for the instance. The name of this configuration is *instance-name-*config, where *instance-name* is the name of the server instance.

instance-name

Your choice of name for the instance that you are creating.

If you are creating a shared instance, specify the configuration that the instance will share with other clusters or instances.

Do *not* specify a cluster.

```
$ asadmin --host das-host [--port admin-port]
create-local-instance [--node node-name] --config configuration-name
instance-name
```

das-host

The name of the host where the DAS is running.

admin-port

The HTTP or HTTPS port on which the DAS listens for administration requests. If the DAS listens on the default port for administration requests, you may omit this option.

node-name

The node on which the instance is to reside.

If you are creating the instance on a host for which fewer than two nodes are defined, you may omit this option.

If no nodes are defined for the host, GlassFish Server creates a CONFIG node for you. The name of the node is the unqualified name of the host.

If one node is defined for the host, the instance is created on that node.

configuration-name

The name of the existing named configuration that the instance will reference.

instance-name

Your choice of name for the instance that you are creating.

If you are creating a clustered instance, specify the cluster to which the instance will belong.

If the instance is managed by GMS and resides on a node that represents a multihome host, specify the GMS-BIND-INTERFACE-ADDRESS-cluster-name system property.

```
$ asadmin --host das-host [--port admin-port]
create-local-instance --cluster cluster-name [--node node-name]
[--systemproperties
GMS-BIND-INTERFACE-ADDRESS-cluster-name=bind-address]instance-name
```

das-host

The name of the host where the DAS is running.

admin-port

The HTTP or HTTPS port on which the DAS listens for administration requests. If the DAS listens on the default port for administration requests, you may omit this option.

cluster-name

The name of the cluster to which you are adding the instance.

node-name

The node on which the instance is to reside.

If you are creating the instance on a host for which fewer than two nodes are defined, you may omit this option.

If no nodes are defined for the host, GlassFish Server creates a CONFIG node for you. The name of the node is the unqualified name of the host.

If one node is defined for the host, the instance is created on that node.

bind-address

The IP address of the network interface to which GMS binds. Specify this option only if the instance is managed by GMS and resides on a node that represents a multihome host.

instance-name

Your choice of name for the instance that you are creating.

Example 5-10 Creating a Clustered Instance Locally Without Specifying a Node

This example adds the instance kui-i1 to the cluster kuicluster locally. The CONFIG node xk01 is created automatically to represent the host xk01.example.com, on which this example is run. The DAS is running on the host dashost.example.com and listens for administration requests on the default port.

The commands to list the nodes in the domain are included in this example only to demonstrate the creation of the node xk01. These commands are not required to create the instance.

```
$ asadmin --host dashost.example.com list-nodes --long
NODE NAME TYPE NODE HOST INSTALL DIRECTORY REFERENCED BY
localhost-domain1 CONFIG localhost /export/glassfish3
Command list-nodes executed successfully.
$ asadmin --host dashost.example.com
create-local-instance --cluster kuicluster kui-i1
Rendezvoused with DAS on dashost.example.com: 4848.
Port Assignments for server instance kui-i1:
JMX_SYSTEM_CONNECTOR_PORT=28687
JMS_PROVIDER_PORT=27677
HTTP LISTENER PORT=28081
ASADMIN LISTENER PORT=24849
JAVA_DEBUGGER_PORT=29009
IIOP_SSL_LISTENER_PORT=23820
IIOP_LISTENER_PORT=23700
OSGI_SHELL_TELNET_PORT=26666
HTTP SSL LISTENER PORT=28182
IIOP_SSL_MUTUALAUTH_PORT=23920
Command create-local-instance executed successfully.
$ asadmin --host dashost.example.com list-nodes --long
NODE NAME TYPE NODE HOST INSTALL DIRECTORY REFERENCED BY localhost-domain1 CONFIG localhost /export/glassfish3
       CONFIG xk01.example.com /export/glassfish3 kui-i1
Command list-nodes executed successfully.
```

Example 5–11 Creating a Clustered Instance Locally

This example adds the instance yml-i1 to the cluster ymlcluster locally. The instance resides on the node sj01. The DAS is running on the host das1.example.com and listens for administration requests on the default port.

```
$ asadmin --host das1.example.com
create-local-instance --cluster ymlcluster --node sj01 yml-i1
```

```
Rendezvoused with DAS on das1.example.com:4848.
Port Assignments for server instance yml-i1:
JMX_SYSTEM_CONNECTOR_PORT=28687
JMS_PROVIDER_PORT=27677
HTTP_LISTENER_PORT=28081
ASADMIN LISTENER PORT=24849
JAVA_DEBUGGER_PORT=29009
IIOP_SSL_LISTENER_PORT=23820
IIOP_LISTENER_PORT=23700
OSGI_SHELL_TELNET_PORT=26666
HTTP_SSL_LISTENER_PORT=28182
IIOP SSL MUTUALAUTH PORT=23920
Command create-local-instance executed successfully.
```

See Also

- To Create a DCOM Node
- To Create an SSH Node
- To Create a CONFIG Node
- create-local-instance(1)

You can also view the full syntax and options of the subcommand by typing asadmin help create-local-instance at the command line.

Next Steps

After creating an instance, you can start the instance as explained in the following sections:

- To Start an Individual Instance Centrally
- To Stop an Individual Instance Locally

To Delete an Instance Locally

Use the delete-local-instance subcommand in remote mode to delete a GlassFish Server instance locally.

Caution: If you are using a Java Message Service (JMS) cluster with a master broker, do not delete the instance that is associated with the master broker. If this instance must be deleted, use the change-master-broker subcommand to assign the master broker to a different instance.

Deleting an instance involves the following:

- Removing the instance from the configuration of the DAS
- Deleting the instance's files from file system

Before You Begin

Ensure that the instance that you are deleting is not running. For information about how to stop an instance, see the following sections:

- To Stop an Individual Instance Centrally
- To Stop an Individual Instance Locally

1. Ensure that the DAS is running.

Remote subcommands require a running server.

- **2.** Log in to the host that is represented by the node where the instance resides.
- **3.** Confirm that the instance is not running.

```
$ asadmin --host das-host [--port admin-port]
list-instances instance-name
```

das-host

The name of the host where the DAS is running.

admin-port

The HTTP or HTTPS port on which the DAS listens for administration requests. If the DAS listens on the default port for administration requests, you may omit this option.

instance-name

The name of the instance that you are deleting.

4. Run the delete-local-instance subcommand.

```
$ asadmin --host das-host [--port admin-port]
delete-local-instance [--node node-name]instance-name
```

das-host

The name of the host where the DAS is running.

admin-port

The HTTP or HTTPS port on which the DAS listens for administration requests. If the DAS listens on the default port for administration requests, you may omit this option.

node-name

The node on which the instance resides. If only one node is defined for the GlassFish Server installation that you are running on the node's host, you may omit this option.

instance-name

The name of the instance that you are deleting.

Example 5-12 Deleting an Instance Locally

This example confirms that the instance yml-i1 is not running and deletes the instance.

```
$ asadmin --host das1.example.com list-instances yml-i1
yml-i1 not running
Command list-instances executed successfully.
$ asadmin --host das1.example.com delete-local-instance --node sj01 yml-i1
Command delete-local-instance executed successfully.
```

See Also

- To Stop an Individual Instance Centrally
- To Stop an Individual Instance Locally

- change-master-broker(1)
- delete-local-instance(1)
- list-instances(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-local-instance
- asadmin help list-instances

To Start an Individual Instance Locally

Use the start-local-instance subcommand in local mode to start an individual instance locally.

- 1. Log in to the host that is represented by the node where the instance resides.
- Run the start-local-instance subcommand.

```
$ asadmin start-local-instance [--node node-name]instance-name
```

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for controlling the behavior of the instance, see the start-local-instance(1) help page.

node-name

The node on which the instance resides. If only one node is defined for the GlassFish Server installation that you are running on the node's host, you may omit this option.

instance-name

The name of the instance that you are starting.

Example 5-13 Starting an Individual Instance Locally

This example starts the instance yml-i1 locally. The instance resides on the node sj01.

```
$ asadmin start-local-instance --node sj01 yml-i1
Waiting for yml-i1 to start .....
```

```
Successfully started the instance: yml-i1
instance Location: /export/glassfish3/glassfish/nodes/sj01/yml-i1
Log File: /export/glassfish3/glassfish/nodes/sj01/yml-i1/logs/server.log
Admin Port: 24849
Command start-local-instance executed successfully.
```

See Also

```
start-local-instance(1)
```

You can also view the full syntax and options of the subcommand by typing asadmin help start-local-instance at the command line.

Next Steps

After starting an instance, you can deploy applications to the instance. For more information, see the GlassFish Server Open Source Edition Application Deployment Guide.

To Stop an Individual Instance Locally

Use the stop-local-instance subcommand in local mode to stop an individual instance locally.

When an instance is stopped, the instance stops accepting new requests and waits for all outstanding requests to be completed.

- 1. Log in to the host that is represented by the node where the instance resides.
- **2.** Run the stop-local-instance subcommand.

```
$ asadmin stop-local-instance [--node node-name]instance-name
```

node-name

The node on which the instance resides. If only one node is defined for the GlassFish Server installation that you are running on the node's host, you may omit this option.

instance-name

The name of the instance that you are stopping.

Example 5-14 Stopping an Individual Instance Locally

This example stops the instance yml-i1 locally. The instance resides on the node sj01.

```
$ asadmin stop-local-instance --node sj01 yml-i1
Waiting for the instance to stop ....
Command stop-local-instance executed successfully.
```

See Also

```
stop-local-instance(1)
```

You can also view the full syntax and options of the subcommand by typing asadmin help stop-local-instance at the command line.

Troubleshooting

If the instance has become unresponsive and fails to stop, run the subcommand again with the --kill option set to true. When this option is true, the subcommand uses functionality of the operating system to kill the instance process.

To Restart an Individual Instance Locally

Use the restart-local-instance subcommand in local mode to restart an individual instance locally.

When this subcommand restarts an instance, the DAS synchronizes the instance with changes since the last synchronization as described in Default Synchronization for Files and Directories.

If you require different synchronization behavior, stop and start the instance as explained in To Resynchronize an Instance and the DAS Online.

- 1. Log in to the host that is represented by the node where the instance resides.
- **2.** Run the restart-local-instance subcommand.

```
$ asadmin restart-local-instance [--node node-name]instance-name
```

node-name

The node on which the instance resides. If only one node is defined for the GlassFish Server installation that you are running on the node's host, you may omit this option.

instance-name

The name of the instance that you are restarting.

Example 5-15 Restarting an Individual Instance Locally

This example restarts the instance yml-i1 locally. The instance resides on the node sj01.

```
$ asadmin restart-local-instance --node sj01 yml-i1
Command restart-local-instance executed successfully.
```

See Also

restart-local-instance(1)

You can also view the full syntax and options of the subcommand by typing asadmin help restart-local-instance at the command line.

Troubleshooting

If the instance has become unresponsive and fails to stop, run the subcommand again with the --kill option set to true. When this option is true, the subcommand uses functionality of the operating system to kill the instance process before restarting the instance.

Resynchronizing GlassFish Server Instances and the DAS

Configuration data for a GlassFish Server instance is stored as follows:

- In the repository of the domain administration server (DAS)
- In a cache on the host that is local to the instance

The configuration data in these locations must be synchronized. The cache is synchronized in the following circumstances:

- Whenever an asadmin subcommand is run. For more information, see "Impact of Configuration Changes" in GlassFish Server Open Source Edition Administration
- When a user uses the administration tools to start or restart an instance.

Default Synchronization for Files and Directories

The --sync option of the subcommands for starting an instance controls the type of synchronization between the DAS and the instance's files when the instance is started. You can use this option to override the default synchronization behavior for the files and directories of an instance. For more information, see To Resynchronize an Instance and the DAS Online.

On the DAS, the files and directories of an instance are stored in the domain-dir directory, where *domain-dir* is the directory in which a domain's configuration is stored. The default synchronization behavior for the files and directories of an instance is as follows:

applications

This directory contains a subdirectory for each application that is deployed to the instance.

By default, only a change to an application's top-level directory within the application directory causes the DAS to synchronize that application's directory. When the DAS resynchronizes the applications directory, all the application's files and all generated content that is related to the application are copied to the instance.

If a file below a top-level subdirectory is changed without a change to a file in the top-level subdirectory, full synchronization is required. In normal operation, files below the top-level subdirectories of these directories are not changed and such files should not be changed by users. If an application is deployed and undeployed, full synchronization is not necessary to update the instance with the change.

config

This directory contains configuration files for the entire domain.

By default, the DAS resynchronizes files that have been modified since the last resynchronization only if the domain.xml file in this directory has been modified.

> **Note:** If you add a file to the config directory of an instance, the file is deleted when the instance is resynchronized with the DAS. However, any file that you add to the config directory of the DAS is *not* deleted when instances and the DAS are resynchronized. By default, any file that you add to the config directory of the DAS is not resynchronized. If you require any additional configuration files to be resynchronized, you must specify the files explicitly. For more information, see To Resynchronize Additional Configuration Files.

config

config/config-name

This directory contains files that are to be shared by all instances that reference the named configuration config-name. A config-name directory exists for each named configuration in the configuration of the DAS.

Because the *config-name* directory contains the subdirectories lib and docroot, this directory might be very large. Therefore, by default, only a change to a file or a top-level subdirectory of config-name causes the DAS to resynchronize the config-name directory.

config/domain.xml

This file contains the DAS configuration for the domain to which the instance belongs.

By default, the DAS resynchronizes this file if it has been modified since the last resynchronization.

Note: A change to the config/domain.xml file is required to cause the DAS to resynchronize an instance's files. If the config/domain.xml file has not changed since the last resynchronization, none of the instance's files is resynchronized, even if some of these files are out of date in the cache.

docroot

This directory is the HTTP document root directory. By default, all instances in a domain use the same document root directory. To enable instances to use a different document root directory, a virtual server must be created in which the docroot property is set. For more information, see the create-virtual-server(1) help page.

The docroot directory might be very large. Therefore, by default, only a change to a file or a subdirectory in the top level of the docroot directory causes the DAS to resynchronize the docroot directory. The DAS checks files in the top level of the docroot directory to ensure that changes to the index.html file are detected.

When the DAS resynchronizes the docroot directory, all modified files and subdirectories at any level are copied to the instance.

If a file below a top-level subdirectory is changed without a change to a file in the top-level subdirectory, full synchronization is required.

generated

This directory contains generated files for Java EE applications and modules, for example, EJB stubs, compiled JSP classes, and security policy files. Do not modify the contents of this directory.

This directory is resynchronized when the applications directory is resynchronized. Therefore, only directories for applications that are deployed to the instance are resynchronized.

java-web-start

This directory is *not* resynchronized. It is created and populated as required on each instance.

lib

lib/classes

These directories contain common Java class files or JAR archives and ZIP archives for use by applications that are deployed to the entire domain. Typically, these directories contain common JDBC drivers and other utility libraries that are shared by all applications in the domain.

The contents of these directories are loaded by the common class loader. For more information, see "Using the Common Class Loader" in GlassFish Server Open Source Edition Application Development Guide. The class loader loads the contents of these directories in the following order:

- lib/classes
- 2. lib/*.jar
- lib/*.zip

The lib directory also contains the following subdirectories:

applibs

This directory contains application-specific Java class files or JAR archives and ZIP archives for use by applications that are deployed to the entire domain.

ext

This directory contains optional packages in JAR archives and ZIP archives for use by applications that are deployed to the entire domain. These archive files are loaded by using Java extension mechanism. For more information, see Optional Packages - An Overview

(http://download.oracle.com/javase/6/docs/technotes/guides/ex tensions/extensions.html).

Note: Optional packages were formerly known as standard extensions or extensions.

The lib directory and its subdirectories typically contain only a small number of files. Therefore, by default, a change to any file in these directories causes the DAS to resynchronize the file that changed.

To Resynchronize an Instance and the DAS Online

Resynchronizing an instance and the DAS updates the instance with changes to the instance's configuration files on the DAS. An instance is resynchronized with the DAS when the instance is started or restarted.

Note: Resynchronization of an instance is only required if the instance is stopped. A running instance does not require resynchronization.

- **1.** Ensure that the DAS is running.
- **2.** Determine whether the instance is stopped.

asadmin> list-instances instance-name

instance-name

The name of the instance that you are resynchronizing with the DAS.

If the instance is stopped, the list-instances subcommand indicates that the instance is not running.

If the instance is stopped, start the instance.

If the instance is running, no further action is required.

If DCOM or SSH is set up, start the instance centrally.

If you require full synchronization, set the --sync option of the start-instance subcommand to full. If default synchronization is sufficient, omit this option.

asadmin> start-instance [--sync full] instance-name

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for controlling the behavior of the instance, see the start-instance(1) help page.

instance-name

The name of the instance that you are starting.

If neither DCOM nor SSH is set up, start the instance locally from the host where the instance resides.

If you require full synchronization, set the --sync option of the start-local-instance subcommand to full. If default synchronization is sufficient, omit this option.

```
$ asadmin start-local-instance [--node node-name] [--sync full]
instance-name
```

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for controlling the behavior of the instance, see the start-local-instance(1) help page.

node-name

The node on which the instance resides. If only one node is defined for the GlassFish Server installation that you are running on the node's host, you may omit this option.

instance-name

The name of the instance that you are starting.

Example 5–16 Resynchronizing an Instance and the DAS Online

This example determines that the instance yml-i1 is stopped and fully resynchronizes the instance with the DAS. Because neither DCOM nor SSH is set up, the instance is started locally on the host where the instance resides. In this example, multiple nodes are defined for the GlassFish Server installation that is running on the node's host.

To determine whether the instance is stopped, the following command is run in multimode on the DAS host:

```
asadmin> list-instances yml-i1
yml-i1 not running
Command list-instances executed successfully.
```

To start the instance, the following command is run in single mode on the host where the instance resides:

```
$ asadmin start-local-instance --node sj01 --sync full yml-i1
Removing all cached state for instance yml-i1.
Waiting for yml-i1 to start .....
Successfully started the instance: yml-i1
instance Location: /export/glassfish3/glassfish/nodes/sj01/yml-i1
Log File: /export/glassfish3/glassfish/nodes/sj01/yml-i1/logs/server.log
Admin Port: 24849
Command start-local-instance executed successfully.
```

See Also

- list-instances(1)
- start-instance(1)
- start-local-instance(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line.

```
asadmin help list-instances
asadmin help start-instance
asadmin help start-local-instance
```

To Resynchronize Library Files

To ensure that library files are resynchronized correctly, you must ensure that each library file is placed in the correct directory for the type of file.

Place each library file in the correct location for the type of library file as shown in the following table.

Type of Library Files	Location
Common JAR archives and ZIP archives for all applications in a domain.	domain-dir/lib
Common Java class files for a domain for all applications in a domain.	domain-dir/lib/classes
Application-specific libraries.	domain-dir/lib/applibs
Optional packages for all applications in a domain.	domain-dir/lib/ext
Library files for all applications that are deployed to a specific cluster or standalone instance.	domain-dir/config/config-name/lib
Optional packages for all applications that are deployed to a specific cluster or standalone instance.	domain-dir/config/config-name/lib/ext

domain-dir

The directory in which the domain's configuration is stored.

config-name

For a standalone instance: the named configuration that the instance references.

For a clustered instance: the named configuration that the cluster to which the instance belongs references.

2. When you deploy an application that depends on these library files, use the --libraries option of the deploy subcommand to specify these dependencies.

For library files in the *domain-dir*/lib/applib directory, only the JAR file name is required, for example:

asadmin> deploy --libraries commons-coll.jar,X1.jar app.ear

For other types of library file, the full path is required.

See Also

deploy(1)

You can also view the full syntax and options of the subcommands by typing the command asadmin help deploy at the command line.

To Resynchronize Custom Configuration Files for an Instance

Configuration files in the *domain-dir*/config directory that are resynchronized are resynchronized for the entire domain. If you create a custom configuration file for an instance or a cluster, the custom file is resynchronized only for the instance or cluster.

1. Place the custom configuration file in the *domain-dir*/config/*config-name* directory.

domain-dir

The directory in which the domain's configuration is stored.

config-name

The named configuration that the instance references.

- **2.** If the instance locates the file through an option of the Java application launcher, update the option.
 - **a.** Delete the option.

```
asadmin> delete-jvm-options --target instance-name
option-name=current-value
```

instance-name

The name of the instance for which the custom configuration file is created.

option-name

The name of the option for locating the file.

current-value

The current value of the option for locating the file.

b. Re-create the option that you deleted in the previous step.

```
asadmin> create-jvm-options --target instance-name
option-name=new-value
```

instance-name

The name of the instance for which the custom configuration file is created.

option-name

The name of the option for locating the file.

new-value

The new value of the option for locating the file.

Example 5-17 Updating the Option for Locating a Configuration File

This example updates the option for locating the server.policy file to specify a custom file for the instance pmd.

```
asadmin> delete-jvm-options --target pmd
-Djava.security.policy=${com.sun.aas.instanceRoot}/config/server.policy
Deleted 1 option(s)
Command delete-jvm-options executed successfully.
asadmin> create-jvm-options --target pmd
-Djava.security.policy=${com.sun.aas.instanceRoot}/config/pmd-config/server.policy
Created 1 option(s)
Command create-jvm-options executed successfully.
```

See Also

- create-jvm-options(1)
- delete-jvm-options(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line.

```
asadmin help create-jvm-options
asadmin help delete-jvm-options
```

To Resynchronize Users' Changes to Files

A change to the config/domain.xml file is required to cause the DAS to resynchronize instances' files. If other files in the domain directory are changed without a change to the config/domain.xml file, instances are not resynchronized with these changes.

The following changes are examples of changes to the domain directory without a change to the config/domain.xml file:

- Adding files to the lib directory
- Adding certificates to the key store by using the keytool command
- Change the last modified time of the config/domain.xml file. Exactly how to change the last modified time depends on the operating system.

For example, on UNIX and Linux systems, you can use the touch(1) command.

Resynchronize each instance in the domain with the DAS. For instructions, see To Resynchronize an Instance and the DAS Online.

See Also

- To Resynchronize an Instance and the DAS Online
- touch(1)

To Resynchronize Additional Configuration Files

By default, GlassFish Server synchronizes only the following configuration files:

- admin-keyfile
- cacerts.jks
- default-web.xml
- domain.xml
- domain-passwords
- kevfile
- keystore.jks
- server.policy
- sun-acc.xml
- wss-server-config-1.0
- xml wss-server-config-2.0.xml

If you require instances in a domain to be resynchronized with additional configuration files for the domain, you can specify a list of files to resynchronize.

> **Caution:** If you specify a list of files to resynchronize, you must specify *all* the files that the instances require, including the files that GlassFish Server resynchronizes by default. Any file in the instance's cache that is not in the list is deleted when the instance is resynchronized with the DAS.

In the config directory of the domain, create a plain text file that is named config-files that lists the files to resynchronize.

In the config-files file, list each file name on a separate line.

Example 5-18 config-files File

This example shows the content of a config-files file. This file specifies that the some-other-info file is to be resynchronized in addition to the files that GlassFish Server resynchronizes by default:

```
admin-keyfile
cacerts.jks
default-web.xml
domain.xml
domain-passwords
keyfile
keystore.jks
server.policy
sun-acc.xml
wss-server-config-1.0.xml
wss-server-config-2.0.xml
some-other-info
```

To Prevent Deletion of Application-Generated Files

When the DAS resynchronizes an instance's files, the DAS deletes from the instance's cache any files that are not listed for resynchronization. If an application creates files in a directory that the DAS resynchronizes, these files are deleted when the DAS resynchronizes an instance with the DAS.

Put the files in a subdirectory under the domain directory that is not defined by GlassFish Server, for example,

/export/glassfish3/glassfish/domains/domain1/myapp/myfile.

To Resynchronize an Instance and the DAS Offline

Resynchronizing an instance and the DAS offline updates the instance's cache without the need for the instance to be able to communicate with the DAS. Offline resynchronization is typically required for the following reasons:

- To reestablish the instance after an upgrade
- To synchronize the instance manually with the DAS when the instance cannot contact the DAS
- Ensure that the DAS is running.
- Export the configuration data that you are resynchronizing to an archive file.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for exporting the configuration data, see the export-sync-bundle(1) help page.

How to export the data depends on the host from where you run the export-sync-bundle subcommand.

From the DAS host, run the export-sync-bundle subcommand as follows:

```
asadmin> export-sync-bundle --target target
```

target

The cluster or standalone instance for which to export configuration data.

Do not specify a clustered instance. If you specify a clustered instance, an error occurs. To export configuration data for a clustered instance, specify the name of the cluster of which the instance is a member, not the instance.

The file is created on the DAS host.

From the host where the instance resides, run the export-sync-bundle subcommand as follows:

```
$ asadmin --host das-host [--port admin-port]
export-sync-bundle [--retrieve=true] --target target
```

The name of the host where the DAS is running.

admin-port

The HTTP or HTTPS port on which the DAS listens for administration requests. If the DAS listens on the default port for administration requests, you may omit this option.

target

The cluster or standalone instance for which to export configuration data.

Do not specify a clustered instance. If you specify a clustered instance, an error occurs. To export configuration data for a clustered instance, specify the name of the cluster of which the instance is a member, not the instance.

Note: To create the archive file on the host where the instance resides, set the --retrieve option to true. If you omit this option, the archive file is created on the DAS host.

- **3.** If necessary, copy the archive file that you created in Step 2 from the DAS host to the host where the instance resides.
- From the host where the instance resides, import the instance's configuration data from the archive file that you created in Step 2.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for importing the configuration data, see the import-sync-bundle(1) help page.

```
$ asadmin import-sync-bundle [--node node-name] --instance instance-name
archive-file
```

node-name

The node on which the instance resides. If you omit this option, the subcommand determines the node from the DAS configuration in the archive file.

instance-name

The name of the instance that you are resynchronizing.

archive-file

The name of the file, including the path, that contains the archive file to import.

Example 5–19 Resynchronizing an Instance and the DAS Offline

This example resynchronizes the clustered instance yml-i1 and the DAS offline. The instance is a member of the cluster ymlcluster. The archive file that contains the instance's configuration data is created on the host where the instance resides.

```
$ asadmin --host dashost.example.com
export-sync-bundle --retrieve=true --target ymlcluster
Command export-sync-bundle executed successfully.
$ asadmin import-sync-bundle --node sj01
--instance yml-i1 ymlcluster-sync-bundle.zip
Command import-sync-bundle executed successfully.
```

See Also

- export-sync-bundle(1)
- import-sync-bundle(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line.

```
asadmin help export-sync-bundle
asadmin help import-sync-bundle
```

Migrating EJB Timers

If a GlassFish Server server instance stops or fails abnormally, it may be desirable to migrate the EJB timers defined for that stopped server instance to another running server instance.

Automatic timer migration is enabled by default for clustered server instances that are stopped normally. Automatic timer migration can also be enabled to handle clustered server instance crashes. In addition, timers can be migrated manually for stopped or crashed server instances.

- To Enable Automatic EJB Timer Migration for Failed Clustered Instances
- To Migrate EJB Timers Manually

To Enable Automatic EJB Timer Migration for Failed Clustered Instances

Automatic migration of EJB timers is enabled by default for clustered server instances that are stopped normally. If the Group Management Service (GMS) is enabled and a clustered instance is stopped normally, no further action is required for timer migration to occur. The procedure in this section is only necessary if you want to enable automatic timer migration for clustered server instances that have stopped abnormally.

Note: If the GMS is enabled, the default automatic timer migration cannot be disabled. To disable automatic timer migration, you must first disable the GMS. For information about the GMS, see Group Management Service.

Before You Begin

Automatic EJB timer migration can only be configured for clustered server instances. Automatic timer migration is not possible for standalone server instances.

Enable delegated transaction recovery for the cluster.

This enables automatic timer migration for failed server instances in the cluster.

For instructions on enabling delegated transaction recovery, see "Administering Transactions" in GlassFish Server Open Source Edition Administration Guide.

To Migrate EJB Timers Manually

EJB timers can be migrated manually from a stopped source instance to a specified target instance in the same cluster if GMS notification is not enabled. If no target instance is specified, the DAS will attempt to find a suitable server instance. A migration notification will then be sent to the selected target server instance.

Note the following restrictions:

- If the source instance is part of a cluster, then the target instance must also be part of that same cluster.
- It is not possible to migrate timers from a standalone instance to a clustered instance, or from one cluster to another cluster.
- It is not possible to migrate timers from one standalone instance to another standalone instance.
- All EJB timers defined for a given instance are migrated with this procedure. It is not possible to migrate individual timers.

Before You Begin

The server instance from which the EJB timers are to be migrated should not be active during the migration process.

Verify that the source clustered server instance from which the EJB timers are to be migrated is not currently running.

```
asadmin> list-instances source-instance
```

2. Stop the instance from which the timers are to be migrated, if that instance is still running.

```
asadmin> stop-instance source-instance
```

Note: The target instance to which the timers will be migrated should be running.

3. List the currently defined EJB timers on the source instance, if desired.

```
asadmin> list-timers source-cluster
```

4. Migrate the timers from the stopped source instance to the target instance.

```
asadmin> migrate-timers --target target-instance source-instance
```

Example 5–20 Migrating an EJB Timer

The following example show how to migrate timers from a clustered source instance named football to a clustered target instance named soccer.

asadmin> migrate-timers --target soccer football

See Also

list-timers(1), migrate-timers(1), list-instances(1), stop-instance(1)

Administering Named Configurations

A named configuration is a set of configuration information for GlassFish Server instances and clusters. A configuration sets port numbers for listeners that an instance or a cluster uses and defines settings for items such as the EJB container, security, logging, and monitoring. Applications and resources are not defined in named configurations.

GlassFish Server enables you to create configurations for use by clusters and instances. GlassFish Server creates configurations automatically for clusters and instances that do not reference an existing configuration. You can modify any existing named configuration regardless of how the configuration was created.

The following topics are addressed here:

- **About Named Configurations**
- Creating, Listing, and Deleting Named Configurations
- Modifying Properties for Named Configurations and Instances

About Named Configurations

Configurations exist in a domain. Multiple GlassFish Server instances or clusters in the domain can reference the same configuration, or they can have separate configurations. To ensure that the environment in a cluster's instances is homogenous, all instances in the cluster inherit the cluster's configuration.

Types of Named Configurations

Each named configuration is one of the following types of configuration:

Standalone configuration

A standalone configuration is referenced by only one instance or cluster and is not shared with any other instances or clusters.

Note: A configuration that is referenced by only one cluster is a standalone configuration, even if the cluster contains multiple instances.

Shared configuration

A shared configuration is referenced by multiple instances or clusters.

The type of an unclustered instance is determined by the type of the configuration that the instance references. For more information, see Types of GlassFish Server Instances.

The default-config Configuration

The default-config configuration is a special configuration that acts as a template for creating named configurations. Clusters and instances cannot refer to the default-config configuration. The default-config configuration can only be copied to create configurations.

Automatically Created Configurations

When you create a cluster or an instance, you can choose whether to specify an existing configuration that the new cluster or instance will reference. If you choose to create a cluster or an instance without specifying an existing configuration, GlassFish Server automatically creates a configuration for the cluster or instance. For more information, see the following sections:

- To Create a Cluster
- To Create an Instance Centrally
- To Create an Instance Locally

GlassFish Server automatically creates a configuration by copying the default-config configuration. If you require an instance or cluster to reference a copy of a different configuration, copy the configuration and specify the copy when you create the instance or cluster. For information about how to copy a configuration, see To Create a Named Configuration.

GlassFish Server assigns the name *cluster-or-instance*-config to an automatically created configuration. cluster-or-instance is the name of the cluster or instance for which the configuration is created. The server-config configuration is automatically created for the domain administration server (DAS) when the domain is created.

Directory for Configuration Synchronization

When a named configuration is created, GlassFish Server creates a configuration directory on the domain administration server (DAS) at domain-dir/config/config-name.

domain-dir

The directory in which the domain's configuration is stored.

config-name

The name that was assigned to the configuration when the configuration was created.

This contents of this directory are synchronized to all instances that inherit or reference the configuration.

Creating, Listing, and Deleting Named Configurations

GlassFish Server enables you to create configurations for use by clusters and instances, obtain information about configurations, and delete configurations that are no longer required.

The following topics are addressed here:

- To Create a Named Configuration
- To List the Named Configurations in a Domain
- To List the Targets of a Named Configuration

To Delete a Named Configuration

To Create a Named Configuration

Use the copy-config subcommand in remote mode to create a named configuration by copying an existing configuration.

GlassFish Server requires you to create a configuration by copying a configuration because a configuration contains many required settings. The newly created configuration is identical to the configuration that you copy until you change its configuration settings.

Tip: Create a named configuration *only* if you plan to share the configuration among multiple unclustered instances or clusters, or if you are using a configuration to preconfigure GMS settings. Otherwise, create clusters and instances without specifying an existing configuration. If no configuration is specified, GlassFish Server creates a copy of the default configuration for the cluster or instance.

For more information, see the following sections:

- To Preconfigure Nondefault GMS Configuration Settings
- To Create a Cluster
- To Create an Instance Centrally
- To Create an Instance Locally
- Ensure that the DAS is running.

Remote subcommands require a running server.

2. Run the copy-config subcommand.

Note: Only the options that are required to complete this task are provided in this step. For information about all the options for configuring the named configuration, see the copy-config(1) help page.

asadmin> copy-config source-config-name destination-config-name

source-config-name

The name of the configuration that you are copying. You must specify a configuration to copy even if you are copying the default configuration. The configuration must already exist.

destination-config-name

Your choice of name for the configuration that you are creating by copying the source configuration.

Example 6-1 Creating a Named Configuration

This example creates the named configuration clusterpresets-config by copying the default configuration.

asadmin> copy-config default-config clusterpresets-config Command copy-config executed successfully.

See Also

- To Preconfigure Nondefault GMS Configuration Settings
- To Create a Cluster
- To Create an Instance Centrally
- To Create an Instance Locally
- copy-config(1)

You can also view the full syntax and options of the subcommand by typing asadmin help copy-config at the command line.

To List the Named Configurations in a Domain

Use the list-configs subcommand in remote mode to list existing named configurations in a domain.

- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- **2.** Run the list-configs subcommand.

```
asadmin> list-configs
```

Example 6–2 Listing All Named Configurations in a Domain

This example lists all named configurations in the current domain.

```
asadmin> list-configs
server-config
default-config
ymlcluster-config
clusterpresets-config
Command list-configs executed successfully.
```

See Also

list-configs(1)

You can also view the full syntax and options of the subcommand by typing asadmin help list-configs at the command line.

To List the Targets of a Named Configuration

Use the list-clusters subcommand and the list-instances subcommand in remote mode to list the targets of a named configuration.

The targets of a named configuration are the clusters and GlassFish Server instances that reference the configuration.

- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- **2.** List the clusters that refer to the configuration.

```
asadmin> list-clusters config-name
```

config-name

The name of the configuration whose targets you are listing.

3. List the instances that refer to the configuration.

```
asadmin> list-instances config-name
```

config-name

The name of the configuration whose targets you are listing.

Example 6-3 Listing the Targets of a Named Configuration

This example shows that the cluster ymlcluster and the instances yml-i1 and yml-i2 reference the named configuration ymlcluster-config.

```
asadmin> list-clusters ymlcluster-config
ymlcluster partially running
Command list-clusters executed successfully.
asadmin> list-instances ymlcluster-config
yml-i1 running
yml-i2 not running
Command list-instances executed successfully.
```

See Also

- list-clusters(1)
- list-instances(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help list-clusters
- asadmin help list-instances

To Delete a Named Configuration

Use the delete-config subcommand in remote mode to delete an existing named configuration from the configuration of the DAS.

You cannot delete the default-config configuration.

Note: A standalone configuration that was created automatically for a cluster or a GlassFish Server instance is deleted when the cluster or instance is deleted.

Before You Begin

Ensure that no clusters or instances refer to the configuration. If a cluster or instance refers to the configuration and is no longer required, delete the cluster or instance. For information about how to delete an instance and how to delete a cluster, see the following sections:

- To Delete an Instance Centrally
- To Delete an Instance Locally
- To Delete a Cluster
- Ensure that the DAS is running.

Remote subcommands require a running server.

2. Confirm that no clusters refer to the configuration that you are deleting.

```
asadmin> list-clusters config-name
```

config-name

The name of the configuration that you are deleting.

3. Confirm that no instances refer to the configuration that you are deleting.

```
asadmin> list-instances config-name
```

config-name

The name of the configuration that you are deleting.

4. Run the delete-config subcommand.

```
asadmin> delete-config config-name
```

config-name

The name of the configuration that you are deleting.

Example 6-4 Deleting a Named Configuration

This example confirms that no clusters or instances refer to the configuration clusterpresets-config and then deletes the configuration.

```
asadmin> list-clusters clusterpresets-config
Nothing to list
Command list-clusters executed successfully.
asadmin> list-instances clusterpresets-config
Nothing to list.
Command list-instances executed successfully.
asadmin> delete-config clusterpresets-config
Command delete-config executed successfully.
```

See Also

- To Delete an Instance Centrally
- To Delete an Instance Locally
- To Delete a Cluster
- delete-config(1)
- list-clusters(1)
- list-instances(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help delete-config
- asadmin help list-clusters
- asadmin help list-instances

Modifying Properties for Named Configurations and Instances

The properties in a named configuration define port numbers for unclustered instances that reference the configuration or clustered instances that inherit the configuration. An instance initially obtains port numbers from the configuration that the instance references or inherits. To avoid port conflicts, edit the properties of named configurations and instances.

The following topics are addressed here:

- Properties for Port Numbers in a Named Configuration
- To Modify a Named Configuration's Properties
- To Modify Port Numbers of an Instance

Properties for Port Numbers in a Named Configuration

The default configuration default-config contains properties that define the initial values of port numbers in a configuration that is copied from default-config. When an instance or a cluster that references the configuration is created, these properties are set for the instance.

You can create additional system properties for a configuration either by specifying the --systemproperties option of the copy-config subcommand or by using the create-system-properties subcommand. To reference a system property from the configuration, use the \${prop-name} \text{ notation, where prop-name is the name of the system property.

For example, if a configuration defines additional HTTP listeners, use system properties to define the ports for those listeners. However, these properties are not set automatically when an instance or a cluster that references the configuration is created. You must set these properties explicitly when you create the instance or cluster.

The properties in a named configuration that define port numbers are as follows:

ASADMIN LISTENER PORT

This property specifies the port number of the HTTP port or HTTPS port through which the DAS connects to the instance to manage the instance. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

HTTP_LISTENER_PORT

This property specifies the port number of the port that is used to listen for HTTP requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

HTTP_SSL_LISTENER_PORT

This property specifies the port number of the port that is used to listen for HTTPS requests. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

IIOP LISTENER PORT

This property specifies the port number of the port that is used for IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

IIOP_SSL_LISTENER_PORT

This property specifies the port number of the port that is used for secure IIOP connections. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

IIOP_SSL_MUTUALAUTH_PORT

This property specifies the port number of the port that is used for secure IIOP connections with client authentication. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

JAVA DEBUGGER PORT

This property specifies the port number of the port that is used for connections to the Java Platform Debugger Architecture (JPDA)

(http://java.sun.com/javase/technologies/core/toolsapis/jpda/) debugger. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

JMS PROVIDER PORT

This property specifies the port number for the Java Message Service provider. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

JMX_SYSTEM_CONNECTOR_PORT

This property specifies the port number on which the JMX connector listens. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

OSGI_SHELL_TELNET_PORT

This property specifies the port number of the port that is used for connections to the Apache Felix Remote Shell

(http://felix.apache.org/site/apache-felix-remote-shell.html).

This shell uses the Felix shell service to interact with the OSGi module management subsystem. Valid values are 1-65535. On UNIX, creating sockets that listen on ports 1-1024 requires superuser privileges.

To Modify a Named Configuration's Properties

Use the get subcommand and the set subcommand in remote mode to modify a named configuration's properties.

You might copy a configuration for use by instances that reside on the same host as instances that refer to the original configuration. In this situation, edit the properties of one of the configurations to ensure that instances that will refer to the configuration have the correct initial settings.

If you change the port number in a configuration, the port number is changed for any instance that references or inherits the configuration.

- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- 2. For each property that you are modifying, determine the current value and set the new value.
 - **a.** Determine the current value of the property.

asadmin> get configs.config.config-name.system-property.property-name.value

config-name

The name of the configuration whose properties you are modifying.

property-name

The name of the property that you are modifying. For a list of available properties, see Properties for Port Numbers in a Named Configuration.

b. Set the property to its new value.

```
asadmin> set
configs.config.config-name.system-property.property-name.value=new-value
```

confia-name

The name of the configuration whose properties you are modifying.

property-name

The name of the property that you are modifying. For a list of available properties, see Properties for Port Numbers in a Named Configuration.

new-value

The value to which you are setting the property.

Example 6–5 Modifying a Property of a Named Configuration

This example changes the value of the JMS_PROVIDER_PORT property in the clusterpresets-config configuration from 27676 to 27678.

```
asadmin> get
```

configs.config.clusterpresets-config.system-property.JMS_PROVIDER_PORT.value configs.config.clusterpresets-config.system-property.JMS_PROVIDER_PORT.value=27676 Command get executed successfully. asadmin> set

configs.config.clusterpresets-config.system-property.JMS_PROVIDER_PORT.value=27678 configs.config.clusterpresets-config.system-property.JMS_PROVIDER_PORT.value=27678 Command set executed successfully.

See Also

- get(1)
- set(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help get
- asadmin help set

To Modify Port Numbers of an Instance

Use the get subcommand and the set subcommand in remote mode to modify the port numbers of an instance.

The port numbers of a instance are initially set in the configuration that the instance references or inherits from its parent cluster. Multiple instances that reside on the same host must each listen on a unique port number. Therefore, if multiple instances that reference or inherit the same configuration reside on the same host, a port conflict prevents all except one of the instances from starting. To avoid port conflicts, modify the port numbers on which individual instances listen.

If you modify an instance's port number and later modify the port number in the instance's configuration, the instance's port number remains unchanged.

The port numbers of an instance are stored as Java system properties. When GlassFish Server is started, it treats these properties in the same way as properties that are passed through the -D option of the Java application launcher.

- **1.** Ensure that the DAS is running.
 - Remote subcommands require a running server.
- 2. For each port number that you are modifying, determine the current value and set the new value.
 - **a.** Determine the current value of the port number.

```
asadmin> get
servers.server.instance-name.system-property.port-property.value
```

instance-name

The name of the instance whose port numbers you are modifying.

port-property

The name of the property that corresponds to the port number that you are modifying. For a list of available properties, see Properties for Port Numbers in a Named Configuration.

b. Set the port number to its new value.

```
asadmin> get
servers.server.instance-name.system-property.port-property.value=new-value
```

instance-name

The name of the instance whose port numbers you are modifying.

port-property

The name of the property that corresponds to the port number that you are modifying. For a list of available properties, see Properties for Port Numbers in a Named Configuration.

new-value

The value to which you are setting the port number.

Example 6-6 Modifying a Port Number for an Instance

This example changes the port number of the HTTP port or the HTTPS port for administration of the pmdsainst instance from 24849 to 24859.

```
asadmin> get
{\tt server.server.pmds ainst.system-property. ASADMIN\_LISTENER\_PORT. value}
servers.server.pmdsainst.system-property.ASADMIN_LISTENER_PORT.value=24849
Command get executed successfully.
asadmin> set
servers.server.pmdsainst.system-property.ASADMIN_LISTENER_PORT.value=24859
servers.server.pmdsainst.system-property.ASADMIN_LISTENER_PORT.value=24859
Command set executed successfully.
```

See Also

■ get(1)

set(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help get
- asadmin help set

Μo	difv	rina	Properties	for	Named	Configurations	and	Instances

Configuring HTTP Load Balancing

This chapter describes how to configure HTTP load balancing on GlassFish Server 4.0. The following topics are addressed here:

Setting Up HTTP Load Balancing

For information on other types of load balancing, see Configuring Java Message Service High Availability and RMI-IIOP Load Balancing and Failover.

Setting Up HTTP Load Balancing

This section describes how to set up load balancing for GlassFish Server.

The following topics are addressed here:

- Prerequisites for Setting Up HTTP Load Balancing
- Configuring GlassFish Server with Apache HTTP Server and mod_jk
- Configuring GlassFish Server with Apache HTTP Server and mod_proxy_ajp
- **HTTP Load Balancer Deployments**

Prerequisites for Setting Up HTTP Load Balancing

Before configuring your load balancer, you must:

- Install a supported web server and configure it. If using the mod_jk or mod_proxy_ ajp modules, the only supported web server is Apache HTTP Server 2.2.x.
- Configure the mod_jk connector module, as described in Configuring GlassFish Server with Apache HTTP Server and mod_jk, or configure the mod_proxy_ajp connector module, as described in Configuring GlassFish Server with Apache HTTP Server and mod_proxy_ajp.
- Create GlassFish Server clusters or server instances to participate in load balancing.
- Deploy applications to these clusters or instances.

Configuring GlassFish Server with Apache HTTP Server and mod_jk

GlassFish Server4.0 can be configured for load balancing with Apache HTTP Server as a front end by enabling the Apache mod_jk connector module. To enable the mod_jk module in GlassFish Server, set the GlassFish Server jk-enabled network-listener attribute. You can also create jk-connectors under different virtual-servers using the jk-enabled network-listener attribute.

To Configure the mod_jk Connector Module

1. Install Apache HTTP Server

```
(http://httpd.apache.org/docs/2.2/install.html) and mod_jk
(http://tomcat.apache.org/connectors-doc/webserver_
howto/apache.html).
```

2. Configure workers.properties and httpd.conf.

For example:

apache2/config/workers.properties

```
# Define 1 real worker using ajp13
worker.list=worker1
# Set properties for worker1 (ajp13)
worker.worker1.type=ajp13
worker.worker1.host=localhost
worker.worker1.port=8009
```

apache2/conf/httpd.conf

```
LoadModule jk_module /Users/Amy/apache2/modules/mod_
jk-1.2.25-httpd-2.2.4.so
JkWorkersFile /Users/Amy/apache2/conf/worker.properties
# Where to put jk logs
JkLogFile /Users/Amy/apache2/logs/mod_jk.log
# Set the jk log level [debug/error/info]
JkLogLevel debug
# Select the log format
JkLogStampFormat "[%a %b %d %H:%M:%S %Y] "
# JkOptions indicate to send SSL KEY SIZE,
JkOptions +ForwardKeySize +ForwardURICompat -ForwardDirectories
# JkRequestLogFormat set the request format
JkRequestLogFormat "%w %V %T"
# Send everything for context /examples to worker named worker1 (ajp13)
JkMount /examples/* worker1
```

- **3.** Start Apache HTTP Server.
- 4. Create a jk-enabled network listener by using the create-network-listener subcommand.

```
asadmin> create-network-listener --protocol http-listener-1 \
--listenerport 8009 --jkenabled true jk-connector
```

5. If you are using the glassfish-jk.properties file, set the jk-configuration-file property of the network listener to the fully-qualified file name of the glassfish-jk.properties file.

```
asadmin> set server-config.network-config.network-listeners.network-listener.\
jk-connector.jk-configuration-file=domain-dir/config/glassfish-jk.properties
```

6. If you expect to need more than five threads for the listener, increase the maximum threads in the http-thread-pool pool:

```
asadmin> set configs.config.server-config.thread-pools.thread-pool.\
http-thread-pool.max-thread-pool-size=value
```

7. Restart GlassFish Server.

Example 7-1 httpd.conf File for Load Balancing

This example shows an httpd.conf file that is set for load balancing.

```
LoadModule jk_module /usr/lib/httpd/modules/mod_jk.so
JkWorkersFile /etc/httpd/conf/worker.properties
# Where to put ik logs
JkLogFile /var/log/httpd/mod_jk.log
# Set the jk log level [debug/error/info]
JkLogLevel debug
# Select the log format
JkLogStampFormat "[%a %b %d %H:%M:%S %Y] "
# JkOptions indicate to send SSL KEY SIZE,
JkOptions +ForwardKeySize +ForwardURICompat -ForwardDirectories
\# JkRequestLogFormat set the request format
JkRequestLogFormat "%w %V %T"
# Send all jsp requests to GlassFish
JkMount /*.jsp worker1
# Send all glassfish-test requests to GlassFish
JkMount /glassfish-test/* loadbalancer
```

Example 7-2 workers.properties File for Load Balancing

This example shows a workers properties or glassfish-jk properties file that is set for load balancing. The worker.worker*.port should match with JK ports you created.

```
worker.list=worker1,worker2,loadbalancer
worker.worker1.type=ajp13
worker.worker1.host=localhost
worker.worker1.port=8009
worker.worker1.lbfactor=1
worker.worker1.socket_keepalive=1
worker.worker1.socket_timeout=300
worker.worker2.type=ajp13
worker.worker2.host=localhost
worker.worker2.port=8010
worker.worker2.lbfactor=1
worker.worker2.socket_keepalive=1
worker.worker2.socket_timeout=300
worker.loadbalancer.type=lb
worker.loadbalancer.balance_workers=worker1,worker2
```

Configuring GlassFish Server with Apache HTTP Server and mod proxy ajp

GlassFish Server4.0 can be configured for load balancing with Apache HTTP Server as a front end by enabling the Apache mod_proxy_ajp connector module. To enable the mod_proxy_ajp module in GlassFish Server, set the GlassFish Server jk-enabled network-listener attribute. You can also create jk-connectors under different virtual-servers using the jk-enabled network-listener attribute.

To Configure the mod proxy ajp Connector Module

- 1. Install Apache HTTP Server (http://httpd.apache.org/docs/2.2/install.html).
- 2. Configure httpd.conf.

For example:

```
LoadModule proxy_module /usr/lib/httpd/modules/mod_proxy.so
LoadModule proxy_ajp_module /usr/lib/httpd/modules/mod_proxy_ajp.so
Listen 1979
NameVirtualHost *:1979
<VirtualHost *:1979>
  ServerName localhost
  ErrorLog /var/log/apache2/ajp.error.log
  CustomLog /var/log/apache2/ajp.log combined
   <Proxy *>
    AddDefaultCharset Off
    Order denv.allow
    Allow from all
   </Proxy>
   ProxyPass / ajp://localhost:8009/
   ProxyPassReverse / ajp://localhost:8009/
</VirtualHost>
```

- **3.** Start Apache HTTP Server.
- 4. Create a jk-enabled network listener by using the create-network-listener subcommand.

```
asadmin> create-network-listener --protocol http-listener-1 \
--listenerport 8009 --jkenabled true jk-connector
```

5. If you expect to need more than five threads for the listener, increase the maximum threads in the http-thread-pool pool:

```
asadmin> set configs.config.server-config.thread-pools.thread-pool.\
http-thread-pool.max-thread-pool-size=value
```

6. Restart GlassFish Server.

HTTP Load Balancer Deployments

You can configure your load balancer in different ways, depending on your goals and environment, as described in the following sections:

- **Using Clustered Server Instances**
- Using Multiple Standalone Instances

Using Clustered Server Instances

The most common way to deploy the load balancer is with a cluster or clusters of server instances. By default all the instances in a cluster have the same configuration and the same applications deployed to them. The load balancer distributes the workload between the server instances and requests fail over from an unhealthy instance to a healthy one. If you've configured HTTP session persistence, session information persists when the request is failed over.

If you have multiple clusters, requests can be load balanced across clusters but are only failed over between the instances in a single cluster. Use multiple clusters in a load balancer to easily enable rolling upgrades of applications. For more information, see Upgrading Applications Without Loss of Availability.

Note: Requests cannot be load balanced across clusters and standalone instances.

Using Multiple Standalone Instances

It is also possible to configure your load balancer to use multiple standalone instances, and load balance and failover requests between them. However, in this configuration, you must manually ensure that the standalone instances have homogenous environments and the same applications deployed to them. Because clusters automatically maintain a homogenous environment, for most situations it is better and easier to use clusters.

Tip: Load balancing across multiple standalone instances only provides failover for requests, and any associated HTTP session data will not be failed over. This is another reason why using a cluster, which can provide session failover, is a more desirable load balancing configuration.

Setting Up HTTP Load Balancir	Setting U) HTTP	Load	Balancing
-------------------------------	-----------	--------	------	-----------

Upgrading Applications Without Loss of Availability

Upgrading an application to a new version without loss of availability to users is called a rolling upgrade. Carefully managing the two versions of the application across the upgrade ensures that current users of the application complete their tasks without interruption, while new users transparently get the new version of the application. With a rolling upgrade, users are unaware that the upgrade occurs.

For more information about application versions and how they are identified, see "Module and Application Versions" in GlassFish Server Open Source Edition Application Deployment Guide.

In a clustered environment, a rolling upgrade redeploys an application with a minimal loss of service and sessions. A session is any artifact that can be replicated, for example:

- HttpSession
- SingleSignOn
- ServletTimer
- DialogFragment
- Stateful session bean

A rolling upgrade can take place under light to moderate loads. The procedure requires about 10-15 minutes for each GlassFish Server instance.

> **Caution:** To prevent the risk of version mismatch when a session fails over, upgrade all instances in a cluster at the same time. Otherwise a session might fail over to an instance where different versions of components are running.

Perform this task on each cluster separately. A cluster acts as a safe boundary for session failover for instances in the cluster. Sessions in one cluster can never fail over to sessions in another cluster. Therefore, the risk of version mismatch is avoided.

Application Compatibility

Rolling upgrades pose varying degrees of difficulty depending on the magnitude of changes between the two application versions.

If the changes are superficial, for example, changes to static text and images, the two versions of the application are *compatible* and can both run at once in the same cluster. Compatible applications must:

- Use the same session information
- Use compatible database schemas
- Have generally compatible application-level business logic
- Use the same physical data source

You can perform a rolling upgrade of a compatible application in either a single cluster or multiple clusters. For more information, see Upgrading In a Single Cluster.

If the two versions of an application do not meet all the above criteria, then the applications are considered *incompatible*. Executing incompatible versions of an application in one cluster can corrupt application data and cause session failover to not function correctly. The problems depend on the type and extent of the incompatibility. It is good practice to upgrade an incompatible application by creating a "shadow cluster" to which to deploy the new version and slowly quiesce the old cluster and application. For more information, see Upgrading Incompatible Applications.

The application developer and administrator are the best people to determine whether application versions are compatible. If in doubt, assume that the versions are incompatible, since this is the safest approach.

Upgrading In a Single Cluster

You can perform a rolling upgrade of an application deployed to a single cluster, providing the cluster's configuration is not shared with any other cluster.

To Upgrade an Application in a Single Cluster

 Deploy the upgraded application to the cluster in a disabled state and with a new version identifier.

For example:

```
asadmin> asadmin deploy --enabled=false --target myCluster myApp:1.1
```

- **2.** Perform the following steps for each server instance in the cluster.
 - Quiesce one server instance in the cluster from the load balancer.

Follow these steps:

- Disable the server instance using asadmin disable-http-lb-server.
- **b.** Export the load balancer configuration file using asadmin export-http-lb-config.
- Copy the exported configuration file to the web server instance's configuration directory.
 - For example, for Sun Java System Web Server, the location is web-server-install-dir/https-host-name/config/loadbalancer.xml.
- **d.** Wait until the timeout has expired.
 - Monitor the load balancer's log file.
- **b.** Enable the upgraded application version on the quiesced server instance.

For example:

```
asadmin> asadmin enable --target instance01 myApp:1.1
```

Enabling the upgraded application version automatically disables the previous version.

- **c.** Test the upgraded application on the server instance to make sure it runs correctly.
- **d.** Re-enable the server instance in load balancer.

Follow these steps:

- Enable the server instance using asadmin enable-http-lb-server.
- **b.** Export the load balancer configuration file using asadmin export-http-lb-config.
- **c.** Copy the configuration file to the web server's configuration directory.

Upgrading in Multiple Clusters

To Upgrade a Compatible Application in Two or More Clusters

Repeat the following procedure for each cluster.

Deploy the upgraded application to one cluster in a disabled state and with a new version identifier.

For example:

```
asadmin> asadmin deploy --enabled=false --target myCluster myApp:1.1
```

- **2.** Quiesce the cluster with the upgraded application from the load balancer.
 - Disable the cluster using asadmin disable-http-lb-server.
 - **b.** Export the load balancer configuration file using asadmin export-http-lb-config.
 - **c.** Copy the exported configuration file to the web server instance's configuration directory.

For example, for Sun Java System Web Server, the location is web-server-install-dir/https-host-name/config/loadbalancer.xml.

d. Wait until the timeout has expired.

Monitor the load balancer's log file.

3. Enable the upgraded application version on the quiesced cluster.

For example:

```
asadmin> asadmin enable --target myCluster myApp:1.1
```

Enabling the upgraded application version automatically disables the previous version.

- **4.** Test the upgraded application on the cluster to make sure it runs correctly.
- Enable the cluster in the load balancer:
 - Enable the cluster using asadmin enable-http-lb-server.

- **b.** Export the load balancer configuration file using asadmin export-http-lb-config.
- **c.** Copy the configuration file to the web server's configuration directory.

Upgrading Incompatible Applications

If the new version of the application is incompatible with the old version, use the following procedure. For information on what makes applications compatible, see Application Compatibility. Also, you must upgrade incompatible application in two or more clusters. If you have only one cluster, create a "shadow cluster" for the upgrade, as described below.

When upgrading an incompatible application:

- Give the new version of the application a different version identifier from the old version of the application. The steps below assume that the application has a new version identifier.
- If the data schemas are incompatible, use different physical data sources after planning for data migration.
- Deploy the new version to a different cluster from the cluster where the old version is deployed.
- Set an appropriately long timeout for the cluster running the old application before you take it offline, because the requests for the application won't fail over to the new cluster. These user sessions will simply fail.

To Upgrade an Incompatible Application by Creating a Second Cluster

- Create a "shadow cluster" on the same or a different set of machines as the existing cluster. If you already have a second cluster, skip this step.
 - **a.** Use the Administration Console to create the new cluster and reference the existing cluster's named configuration.
 - Customize the ports for the new instances on each machine to avoid conflict with existing active ports.
 - **b.** For all resources associated with the cluster, add a resource reference to the newly created cluster using asadmin create-resource-ref.
 - **c.** Create a reference to all other applications deployed to the cluster (except the current upgraded application) from the newly created cluster using asadmin create-application-ref.
 - **d.** Configure the cluster to be highly available using asadmin configure-ha-cluster.
 - Create reference to the newly-created cluster in the load balancer configuration file using asadmin create-http-lb-ref.
- **2.** Give the new version of the application a different version identifier from the old version.
- **3.** Deploy the new application version with the new cluster as the target. Use a different context root or roots.
- **4.** Start the new cluster while the other cluster is still running.
 - The start causes the cluster to synchronize with the domain and be updated with the new application.

- Test the application on the new cluster to make sure it runs correctly.
- Disable the old cluster from the load balancer using asadmin disable-http-lb-server.
- **7.** Set a timeout for how long lingering sessions survive.
- **8.** Enable the new cluster from the load balancer using asadmin enable-http-lb-server.
- **9.** Export the load balancer configuration file using asadmin export-http-lb-config.
- **10.** Copy the exported configuration file to the web server instance's configuration directory.
 - For example, for Sun Java System Web Server, the location is web-server-install-dir/https-host-name/config/loadbalancer.xml.
- 11. After the timeout period expires or after all users of the old application have exited, stop the old cluster and undeploy the old application version.

Upgrading	Incompatible	Applications

Configuring High Availability Session Persistence and Failover

This chapter explains how to enable and configure high availability session persistence.

- Overview of Session Persistence and Failover
- Enabling the High Availability Session Persistence Service
- Stateful Session Bean Failover

Overview of Session Persistence and Failover

GlassFish Server provides high availability session persistence through failover of HTTP session data and stateful session bean (SFSB) session data. Failover means that in the event of an server instance or hardware failure, another server instance in a cluster takes over a distributed session.

For example, Java EE applications typically have significant amounts of session state data. A web shopping cart is the classic example of session state. Also, an application can cache frequently-needed data in the session object. In fact, almost all applications with significant user interactions need to maintain session state.

Note: When using high availability session persistence together with a load balancer, use a load balancer that includes session-based stickiness as part of its load-balancing algorithm. Otherwise, session data can be misdirected or lost. An example of a load balancer that includes session-based stickiness is the Loadbalancer Plug-In available in Oracle GlassFish Server.

The following topics are addressed here:

- Requirements
- Restrictions
- Scope

Requirements

A distributed session can run in multiple Oracle GlassFish Server instances, if:

Each server instance has access to the same session state data. GlassFish Server supports in-memory session replication on other servers in the cluster for

maintaining HTTP session and stateful session bean data. In-memory session replication is enabled by default for GlassFish Server clustered environments if the Group Management Service is enabled.

The use of in-memory replication requires the Group Management Service (GMS) to be enabled. For more information about GMS, see Group Management Service.

If server instances in a cluster are located on different hosts, ensure that the following prerequisites are met:

- To ensure that GMS and in-memory replication function correctly, the hosts must be on the same subnet.
- To ensure that in-memory replication functions correctly, the system clocks on all hosts in the cluster must be synchronized as closely as possible.

Note: GlassFish Server 4.0 does not support High Availability Database (HADB) configurations. Instead, use in-memory replication, as described in High Availability Session Persistence.

- Each server instance has the same distributable web application deployed to it. The web-app element of the web.xml deployment descriptor file must contain the distributable element.
- The web application uses high-availability session persistence. If a non-distributable web application is configured to use high-availability session persistence, the server writes an error to the log file.
- The web application must be deployed using the deploy or deploydir subcommand with the --availabilityenabled option set to true. For more information on these subcommands, see deploy(1) and deploydir(1).

Restrictions

When configuring session persistence and failover, note the following restrictions:

- When a session fails over, any references to open files or network connections are lost. Applications must be coded with this restriction in mind.
- EJB Singletons are created for each server instance in a cluster, and not once per cluster.
- The high availability session persistence service is not compatible with dynamic deployment, dynamic reloading, and autodeployment. These features are for development, not production environments, so you must disable them before enabling the session persistence service. For information about how to disable these features, see the GlassFish Server Open Source Edition Application Deployment Guide.
- GlassFish Server 4.0 does not support High Availability Database (HADB) configurations. Instead, use in-memory replication, as described in High Availability Session Persistence.
- You can only bind certain objects to distributed sessions that support failover. Contrary to the Servlet 2.4 specification, GlassFish Server 4.0 does not throw an IllegalArgumentException if an object type not supported for failover is bound into a distributed session.

You can bind the following objects into a distributed session that supports failover:

- Local home and object references for all EJB components.
- Colocated stateless session, stateful session, or entity bean reference.
- Distributed stateless session, stateful session, or entity bean reference.
- JNDI Context for InitialContext and java:comp/env.
- UserTransaction objects. However, if the instance that fails is never restarted, any prepared global transactions are lost and might not be correctly rolled back or committed.
- Serializable Java types.
- You cannot bind the following object types into sessions that support failover:
 - **JDBC** DataSource
 - Java Message Service (JMS) ConnectionFactory and Destination objects
 - JavaMail Session
 - Connection Factory
 - Administered Objects
 - Web service reference

In general, for these objects, failover will not work. However, failover might work in some cases, if for example the object is serializable.

Scope

The availability service can be enabled for the following scopes, ranging from highest to lowest:

- Cluster
- Standalone server instance (not part of a cluster)
- Web, EJB, or JMS container in a cluster
- Application
- Standalone Web, EJB, or JMS module
- Individual Stateful Session Bean (SFSB)

In general, enabling or disabling availability session persistence for a cluster or container involves setting the boolean availability-service property to true or false by means of the asadmin set subcommand. The availability service is enabled by default for GlassFish Server clusters and all Web, EJB, and JMS containers running in a cluster.

The value set for the availability-service property is inherited by all child objects running in a given cluster or container unless the value is explicitly overridden at the individual module or application level. For example, if the availability-service property is set to true for an EJB container, the availability service will be enabled by default for all EJB modules running in that container.

Conversely, to enable availability at a given scope, you must enable it at all higher levels as well. For example, to enable availability at the application level, you must also enable it at the cluster or server instance and container levels.

Enabling the High Availability Session Persistence Service

This section explains how to configure and enable the high availability session persistence service.

- To Enable Availability for a Cluster, Standalone Instance or Container
- Configuring Availability for Individual Web Applications
- Configuring Replication and Multi-Threaded Concurrent Access to HttpSessions
- Using Single Sign-on with Session Failover
- Using Coherence*Web for HTTP Session Persistence

To Enable Availability for a Cluster, Standalone Instance or Container

This procedure explains how to enable high availability for a cluster as a whole, or for Web, EJB, or JMS containers that run in a cluster, or for a standalone server instance that is not part of a cluster.

1. Create a GlassFish Server cluster.

For more information, see To Create a Cluster.

2. Set up load balancing for the cluster.

For instructions, see Setting Up HTTP Load Balancing.

3. Verify that the cluster and all instances within the cluster for which you want to enable availability is running.

These steps are also necessary when enabling availability for a Web, EJB, or JMS container running in a cluster. The cluster and all instances in the cluster for which you want to enable availability must be running.

a. Verify that the cluster is running.

```
asadmin> list-clusters
```

A list of clusters and their status (running, not running) is displayed. If the cluster for which you want to enable availability is not running, you can start it with the following command:

```
asadmin> start-cluster cluster-name
```

b. Verify that all instances in the cluster are running.

```
asadmin> list-instances
```

A list of instances and their status is displayed. If the instances for which you want to enable availability are not running, you can start them by using the following command for each instance:

```
asadmin> start-instance instance-name
```

- **4.** Use one of the following asadmin set subcommands to enable availability for a specific cluster, or for a specific Web, EJB, or JMS container.
 - For a cluster as a whole

```
asadmin> set
```

 ${\it cluster-name-} {\it config.availability-service.availability-enabled=true}$

For example, for a cluster named c1:

asadmin> set c1-config.availability-service.availability-enabled=true

For the Web container in a cluster

```
asadmin> set cluster-name-config.availability-service \
.web-container-availability.availability-enabled=true
```

For the EJB container in a cluster

```
asadmin> set cluster-name-config.availability-service \
.ejb-container-availability.availability-enabled=true
```

For the JMS container in a cluster

```
asadmin> set cluster-name-config.availability-service \
.jms-availability.availability-enabled=true
```

For a standalone server instance (not part of a cluster)

```
asadmin> set
instance-name-config.availability-service.availability-enabled=true
```

- **5.** Restart the standalone server instance or each server instance in the cluster.
- Enable availability for any SFSB that requires it.

Select methods for which checkpointing the session state is necessary. For more information, see Configuring Availability for an Individual Bean.

7. Make each web module distributable if you want it to be highly available.

For more information, see "Web Module Deployment Guidelines" in GlassFish Server Open Source Edition Application Deployment Guide.

8. Enable availability for individual applications, web modules, or EJB modules during deployment.

See the links below for instructions.

See Also

- Configuring Availability for Individual Web Applications
- Using Single Sign-on with Session Failover

Configuring Availability for Individual Web Applications

To enable and configure availability for an individual web application, edit the application deployment descriptor file, glassfish-web.xml. The settings in an application's deployment descriptor override the web container's availability settings.

The session-manager element's persistence-type attribute determines the type of session persistence an application uses. It must be set to replicated to enable high availability session persistence.

Example

```
<glassfish-web-app> ...
 <session-config>
   <session-manager persistence-type="replicated">
     <manager-properties>
       cproperty name="persistenceFrequency" value="web-method" />
     </manager-properties>
     <store-properties>
```

```
cproperty name="persistenceScope" value="session" />
     </store-properties>
   </session-manager> ...
</session-config> ...
```

Configuring Replication and Multi-Threaded Concurrent Access to HttpSessions

If you are using Memory Replication and your web application involves multiple client threads concurrently accessing the same session ID, then you may experience session loss even without any instance failure. The problem is that the GlassFish Server 4.0 memory replication framework makes use of session versioning. This feature was designed with the more traditional HTTP request/response communication model in mind.

However, for some types of applications, the traditional request/response model does not work. Examples include many Ajax-related frameworks and the use of Frames. Another example is when a page includes many static resources, such as JPG files. In these situations, most browsers will optimize the loading of these resources by using multiple parallel connections, each of which is handled by a separate request processing thread. If the application has already established a session, then this will also involve more than one thread at a time accessing a single HttpSession.

The solution in such cases is to use the relaxVersionSemantics property in the glassfish-web.xml deployment descriptor file for the application. This enables the web container to return for each requesting thread whatever version of the session that is in the active cache regardless of the version number. This is critical when multiple threads are interacting in an essentially non-deterministic fashion with the container.

Example

The following is an example snippet from a glassfish-web.xml file that illustrates where to add the relaxVersionSemantics property.

```
<glassfish-web-app>
 <session-config>
   <session-manager persistence-type="replicated">
     <manager-properties>
   cproperty name="relaxCacheVersionSemantics" value="true"/>
     </manager-properties>
   </session-manager>
 </session-config>
</glassfish-web-app>
```

Using Single Sign-on with Session Failover

In a single application server instance, once a user is authenticated by an application, the user is not required to re-authenticate individually to other applications running on the same instance. This is called *single sign-on*.

For this feature to continue to work even when an HTTP session fails over to another instance in a cluster, single sign-on information must be persisted using in-memory replication. To persist single sign-on information, first, enable availability for the server instance and the web container, then enable single-sign-on state failover.

You can enable single sign-on state failover by using the asadmin set command to set the configuration's

availability-service.web-container-availability.sso-failover-enabled property to true.

For example, use the set command as follows, where config1 is the configuration name:

asadmin> set config1.availability-service.web-container-availability. \ sso-failover-enabled="true"

Single Sign-On Groups

Applications that can be accessed through a single name and password combination constitute a *single sign-on group*. For HTTP sessions corresponding to applications that are part of a single sign-on group, if one of the sessions times out, other sessions are not invalidated and continue to be available. This is because time out of one session should not affect the availability of other sessions.

As a corollary of this behavior, if a session times out and you try to access the corresponding application from the same browser window that was running the session, you are not required to authenticate again. However, a new session is created.

Take the example of a shopping cart application that is a part of a single sign-on group with two other applications. Assume that the session time out value for the other two applications is higher than the session time out value for the shopping cart application. If your session for the shopping cart application times out and you try to run the shopping cart application from the same browser window that was running the session, you are not required to authenticate again. However, the previous shopping cart is lost, and you have to create a new shopping cart. The other two applications continue to run as usual even though the session running the shopping cart application has timed out.

Similarly, suppose a session corresponding to any of the other two applications times out. You are not required to authenticate again while connecting to the application from the same browser window in which you were running the session.

Note: This behavior applies only to cases where the session times out. If single sign-on is enabled and you invalidate one of the sessions using HttpSession.invalidate(), the sessions for all applications belonging to the single sign-on group are invalidated. If you try to access any application belonging to the single sign-on group, you are required to authenticate again, and a new session is created for the client accessing the application.

Using Coherence*Web for HTTP Session Persistence

Built on top of Oracle Coherence, Coherence*Web is an HTTP session management module dedicated to managing session state in clustered environments. Starting with Coherence 3.7 and GlassFish Server 4.0, there is a new feature of Coherence*Web called ActiveCache for GlassFish. ActiveCache for GlassFish provides Coherence*Web functionality in web applications deployed on GlassFish Servers. Within GlassFish Server, Coherence*Web functions as an additional web container persistence type, named coherence-web.

For information about how to configure and deploy Coherence*Web on GlassFish Server, see Using Coherence*Web with GlassFish Server (http://download.oracle.com/docs/cd/E18686 01/coh.37/e18690/glassfish.htm).

Stateful Session Bean Failover

Stateful session beans (SFSBs) contain client-specific state. There is a one-to-one relationship between clients and the stateful session beans. At creation, the EJB container gives each SFSB a unique session ID that binds it to a client.

An SFSB's state can be saved in a persistent store in case a server instance fails. The state of an SFSB is saved to the persistent store at predefined points in its life cycle. This is called

checkpointing. If enabled, checkpointing generally occurs after the bean completes any transaction, even if the transaction rolls back.

However, if an SFSB participates in a bean-managed transaction, the transaction might be committed in the middle of the execution of a bean method. Since the bean's state might be undergoing transition as a result of the method invocation, this is not an appropriate time to checkpoint the bean's state. In this case, the EJB container checkpoints the bean's state at the end of the corresponding method, provided the bean is not in the scope of another transaction when that method ends. If a bean-managed transaction spans across multiple methods, checkpointing is delayed until there is no active transaction at the end of a subsequent method.

The state of an SFSB is not necessarily transactional and might be significantly modified as a result of non-transactional business methods. If this is the case for an SFSB, you can specify a list of checkpointed methods, as described in Specifying Methods to Be Checkpointed

If a distributable web application references an SFSB, and the web application's session fails over, the EJB reference is also failed over.

If an SFSB that uses session persistence is undeployed while the GlassFish Server instance is stopped, the session data in the persistence store might not be cleared. To prevent this, undeploy the SFSB while the GlassFish Server instance is running.

Configuring Availability for the EJB Container

To enable availability for the EJB container use the asadmin set command to set the following three properties for the configuration:

- availability-service.ejb-container-availability.availability-enabled
- availability-service.ejb-container-availability.sfsb-persistence-type
- availability-service.ejb-container-availability.sfsb-ha-persistence-type

For example, if config1 is the configuration name, use the following commands:

```
asadmin> set --user admin --passwordfile password.txt
--host localhost
--port 4849
config1.availability-service.
ejb-container-availability.availability-enabled="true"
asadmin> set --user admin --passwordfile password.txt --host localhost --port
4849
config1.availability-service.
ejb-container-availability.sfsb-persistence-type="file"
asadmin> set --user admin --passwordfile password.txt
--host localhost
--port 4849
config1.availability-service.
ejb-container-availability.sfsb-ha-persistence-type="replicated"
```

Configuring the SFSB Session Store When Availability Is Disabled

If availability is disabled, the local file system is used for SFSB state passivation, but not persistence. To change where the SFSB state is stored, change the Session Store Location setting in the EIB container. For information about configuring store properties, see the Administration Console online help.

Configuring Availability for an Individual Application or EJB Module

You can enable SFSB availability for an individual application or EJB module during deployment:

- If you are deploying with the Administration Console, check the Availability Enabled checkbox.
- If you are deploying using use the asadmin deploy or asadmin deploydir commands, set the --availability enabled option to true. For more information, see deploy(1) and deploydir(1).

Configuring Availability for an Individual Bean

To enable availability and select methods to be checkpointed for an individual SFSB, use the glassfish-ejb-jar.xml deployment descriptor file.

To enable high availability session persistence, set availability-enabled="true" in the ejb element.

Example 9-1 Example of an EJB Deployment Descriptor With Availability Enabled

```
<glassfish-ejb-jar>
   <enterprise-beans>
       <ejb availability-enabled="true">
           <ejb-name>MySFSB</ejb-name>
       </ejb>
   </enterprise-beans>
</glassfish-ejb-jar>
```

Specifying Methods to Be Checkpointed

If enabled, checkpointing generally occurs after the bean completes any transaction, even if the transaction rolls back. To specify additional optional checkpointing of SFSBs at the end of non-transactional business methods that cause important modifications to the bean's state, use the checkpoint-at-end-of-method element in the ejb element of the glassfish-ejb-jar.xml deployment descriptor file.

The non-transactional methods in the checkpoint-at-end-of-method element can be:

- create() methods defined in the home interface of the SFSB, if you want to checkpoint the initial state of the SFSB immediately after creation
- For SFSBs using container managed transactions only, methods in the remote interface of the bean marked with the transaction attribute TX_NOT_SUPPORTED or TX NEVER

For SFSBs using bean managed transactions only, methods in which a bean managed transaction is neither started nor committed

Any other methods mentioned in this list are ignored. At the end of invocation of each of these methods, the EJB container saves the state of the SFSB to persistent store.

Note: If an SFSB does not participate in any transaction, and if none of its methods are explicitly specified in the checkpoint-at-end-of-method element, the bean's state is not checkpointed at all even if availability-enabled="true" for this bean.

For better performance, specify a *small* subset of methods. The methods should accomplish a significant amount of work or result in important modification to the bean's state.

Example 9–2 Example of EJB Deployment Descriptor Specifying Methods Checkpointing

```
<glassfish-ejb-jar>
    <enterprise-beans>
       <ejb availability-enabled="true">
           <ejb-name>ShoppingCartEJB</ejb-name>
            <checkpoint-at-end-of-method>
                <method>
                    <method-name>addToCart</method-name>
                </method>
            </checkpoint-at-end-of-method>
       </ejb>
   </enterprise-beans>
</glassfish-ejb-jar>
```

Configuring Java Message Service High **Availability**

This chapter describes how to configure the high availability features of the Java Message Service (JMS). It covers how to configure Message Queue broker clusters and how to use them to provide connection failover and load balancing, as described in the following topics:

- Using Message Queue Broker Clusters With GlassFish Server
- Connection Failover
- Load-Balanced Delivery to MDBs

Using Message Queue Broker Clusters With GlassFish Server

This section describes how the JMS service uses Message Queue broker clusters to support high-availability JMS messaging in GlassFish Server clusters. It describes the different cluster and broker types that are supported and how to configure them.

The following topics are addressed here:

- About Message Queue Broker Clusters
- Configuring GlassFish Clusters to Use Message Queue Broker Clusters
- To Configure a GlassFish Cluster to Use an Embedded or Local Conventional Broker Cluster With Master Broker
- To Configure a GlassFish Cluster to Use an Embedded or Local Conventional **Broker Cluster of Peer Brokers**
- To Change the Master Broker in an Embedded or Local Broker Cluster
- To Migrate Between Types of Embedded or Local Conventional Broker Clusters
- To Configure a GlassFish Cluster to Use a Local Enhanced Broker Cluster
- To Configure a GlassFish Cluster to Use a Remote Broker Cluster

About Message Queue Broker Clusters

The following discussion provides a brief overview of Message Queue broker clusters. For complete information, see "Broker Clusters" in Open Message Queue Technical Overview.

Message Queue supports two clustering models both of which provide a scalable message service, but with each providing a different level of message service availability:

Conventional broker clusters. A conventional broker cluster provides for *service* availability. When a broker fails, clients connected to the failed broker reconnect to another broker in the cluster. However, messages and state information stored in the failed broker cannot be recovered until the failed broker is brought back online. The broker failure can therefore result in a significant delay and in JMS message order semantics not being preserved.

Message Queue supports two types of conventional cluster, based on where the cluster configuration change record is stored:

- **Conventional cluster with master broker.** In a conventional cluster with a master broker, one of the brokers, designated as the master broker, stores and maintains the cluster configuration change record. The other brokers in the cluster must communicate with the master broker to keep abreast of changes to the cluster configuration. This is the simplest broker cluster to configure, and is the type of broker cluster that GlassFish Server uses by default to support GlassFish clusters.
- **Conventional cluster of peer brokers.** In a conventional cluster of peer brokers, the cluster configuration change record is stored in a JDBC data store accessible to all the brokers. Thus, brokers can access cluster configuration information whether any other brokers in the cluster are running or not.
- **Enhanced broker clusters.** An enhanced broker cluster provides for *data* availability in addition to service availability. When a broker fails, another broker takes over the pending work of the failed broker. The failover broker has access to the failed broker's messages and state information. Clients connected to the failed broker reconnect to the failover broker. In an enhanced cluster, as compared to a conventional cluster, messages owned by the failed broker are delivered by the failover broker as soon as it takes over, and JMS message order semantics are preserved.

By its very nature, an enhanced broker cluster is a cluster of peer brokers.

Note: Despite the message service availability offered by both conventional and enhanced broker clusters, they do not provide a guarantee against failure and the possibility that certain failures, for example in the middle of a transaction, could require that some operations be repeated. It is the responsibility of the messaging application (both producers and consumers) to respond to JMS exceptions appropriately. For information about the kinds of exceptions that can occur and how to respond to them, see "Handling Exceptions When Failover Occurs" in Open Message Queue Developer's Guide for Java Clients.

Configuring GlassFish Clusters to Use Message Queue Broker Clusters

When a GlassFish Server cluster is created, the JMS service automatically configures a Message Queue conventional broker cluster with master broker for the cluster, provided that the JMS host type in the GlassFish Server cluster's configuration is Embedded or Local. The JMS service configures one Message Queue broker for each instance in the GlassFish Server cluster, and designates as master broker the broker associated with the first instance created in the cluster. In the case of Local JMS hosts, the JMS service configures each broker to run on the same host as the instance with which it is associated. In the case of Embedded JMS hosts, the each broker inherently runs on the same host as the instance with which it is associated because it runs in the same JVM as the instance.

The JMS service manages the lifecycle of Embedded and Local JMS hosts, and this management extends to the management of Message Queue broker clusters as Embedded and Local JMS hosts. For a GlassFish cluster whose configuration specifies Embedded or Local JMS host type, the JMS service:

- Creates and manages one Message Queue broker for each instance in the GlassFish cluster, using this broker as the primary JMS host for the instance.
- Maintains the JMS host list for each instance in the GlassFish cluster such that its primary JMS host appears first in its JMS host list.

The JMS service supports the following types of Message Queue broker clusters with GlassFish Server clusters, based on the JMS host type:

Embedded

- Conventional broker cluster with master broker (default)
- Conventional broker cluster of peer brokers

Local

- Conventional broker cluster with master broker (default)
- Conventional broker cluster of peer brokers
- Enhanced broker cluster

Remote

- Conventional broker cluster with master broker; brokers can differ in number from GlassFish instances and can be located on other hosts
- Conventional broker cluster of peer brokers; brokers can differ in number from GlassFish instances and can be located on other hosts
- Enhanced broker cluster; brokers can differ in number from GlassFish instances and can be located on other hosts

The following topics provide instructions for configuring broker clusters in all these contexts.

To Configure a GlassFish Cluster to Use an Embedded or Local Conventional Broker **Cluster With Master Broker**

Use the configure-jms-cluster subcommand in remote asadmin mode to configure a conventional broker cluster with master broker to service a GlassFish Server cluster that uses either Embedded or Local IMS hosts.

Note that this configuration, with Embedded brokers, is the default for GlassFish Server clusters.

Before You Begin

Perform the following steps after you have created the GlassFish Server cluster, but before you have added instances to the cluster or started the cluster.

Caution: Before using this procedure to reconfigure an existing cluster, you must follow the special procedures to migrate to another type of broker cluster, as described in To Migrate Between Types of Embedded or Local Conventional Broker Clusters. Failing to perform these special procedures could lead to data loss or corruption and even render your setup unusable, depending on the JMS operations performed on the existing cluster.

1. Ensure that the server is running.

Remote asadmin subcommands require a running server.

- 2. Configure the GlassFish Server cluster to use a Message Queue conventional broker cluster with master broker by using the configure-jms-cluster subcommand:
 - > asadmin configure-jms-cluster --clustertype=conventional --configstoretype=masterbroker glassfish-cluster-name

See Also

You can also view the full syntax and options of the subcommand by typing asadmin help configure-jms-cluster at the command line.

To Configure a GlassFish Cluster to Use an Embedded or Local Conventional Broker **Cluster of Peer Brokers**

Use the configure-jms-cluster subcommand in remote asadmin mode to configure a conventional broker cluster of peer brokers to service a GlassFish Server cluster that uses Embedded or Local JMS hosts.

Before You Begin

Perform the following steps after you have created the GlassFish Server cluster, but before you have added instances to the cluster or started the cluster.

Caution: Before using this procedure to reconfigure an existing cluster, you must follow the special procedures to migrate to another type of broker cluster, as described in To Migrate Between Types of Embedded or Local Conventional Broker Clusters. Failing to perform these special procedures could lead to data loss or corruption and even render your setup unusable, depending on the JMS operations performed on the existing cluster.

- **1.** Ensure that the server is running.
 - Remote asadmin subcommands require a running server.
- 2. Create a password file with the entry AS_ADMIN_JMSDBPASSWORD specifying the password of the database user.
 - For information about password file entries, see the asadmin(1M) help page.
- Place a copy of, or a link to, the database's JDBC driver . jar file in the appropriate directory, depending on the JMS host type, on each host where a GlassFish Server cluster instance is to run:

- Embedded: as-install-parent/glassfish/lib/install/applications/jmsra
- Local: as-install-parent/mq/lib/ext
- 4. Configure the GlassFish Server cluster to use a Message Queue conventional broker cluster with master broker by using the configure-jms-cluster subcommand:

```
> asadmin --passwordfile password-file configure-jms-cluster
--clustertype=conventional
--configstoretype=shareddb --dbvendor database-vendor-name --dbuser
database-user-name
--dburl database-url --property list-of-database-specific-properties
glassfish-cluster-name
```

See Also

You can also view the full syntax and options of the subcommand by typing asadmin help configure-jms-cluster at the command line.

To Change the Master Broker in an Embedded or Local Broker Cluster

Use the change-master-broker subcommand in remote asadmin mode to change the master broker to a different broker in a conventional broker cluster with master broker serving a GlassFish Server cluster that uses Embedded or Local JMS hosts.

Follow this procedure, for example, before you remove from a GlassFish cluster the instance associated with the current master broker.

Before You Begin

Although not an absolute requirement, you should make sure all GlassFish instances and Message Queue brokers in the cluster are running before using the change-master-broker command in order to avoid later internal configuration synchronization of any unavailable instance or broker.

- **1.** Ensure that the server is running. Remote asadmin subcommands require a running server.
- **2.** Change the master broker by using the change-master-broker subcommand:
 - > asadmin change-master-broker glassfish-clustered-instance-name

See Also

You can also view the full syntax and options of the subcommand by typing asadmin help change-master-broker at the command line.

To Migrate Between Types of Embedded or Local Conventional Broker Clusters

If the need arises to convert from a conventional broker cluster with master broker to a conventional broker cluster of peer brokers, or the reverse, follow the instructions in "Managing Conventional Clusters" in Open Message Queue Administration Guide.

To Configure a GlassFish Cluster to Use a Local Enhanced Broker Cluster

Use the configure-jms-cluster subcommand in remote asadmin mode to configure an enhanced broker cluster to service a GlassFish Server cluster that uses Local JMS hosts.

Before You Begin

Perform the following steps after you have created the GlassFish Server cluster, but before you have added instances to the cluster or started the cluster.

Caution: Before using this procedure to reconfigure an existing cluster, you must follow the special procedures to migrate from a conventional broker cluster to an enhanced broker cluster, as described in "Converting a Conventional Cluster to an Enhanced Cluster" in Open Message Queue Administration Guide. Failing to perform these special procedures could lead to data loss or corruption and even render your setup unusable, depending on the IMS operations performed on the existing cluster.

1. Ensure that the server is running.

Remote asadmin subcommands require a running server.

2. Create a password file with the entry AS_ADMIN_JMSDBPASSWORD specifying the password of the database user.

For information about password file entries, see the asadmin(1M) help page.

- Place a copy of, or a link to, the database's JDBC driver . jar file in the as-install-parent/mq/lib/ext directory on each host where a GlassFish Server cluster instance is to run.
- 4. Configure the GlassFish Server cluster to use a Message Queue enhanced broker cluster by using the configure-jms-cluster subcommand:

```
> asadmin --passwordfile password-file configure-jms-cluster
--clustertype=enhanced
--configstoretype=shareddb --messagestoretype=jdbc
--dbvendor database-vendor-name --dbuser database-user-name --dburl
database-url
--property list-of-database-specific-properties glassfish-cluster-name
```

See Also

You can also view the full syntax and options of the subcommand by typing asadmin help configure-jms-cluster at the command line.

To Configure a GlassFish Cluster to Use a Remote Broker Cluster

Before You Begin

Perform the following steps after you have:

- Used Message Queue to create a broker cluster.
- Created the GlassFish Server cluster, but not yet created instances for the cluster.
- Ensure that the server is running.

The remote subcommands used in this procedure require a running server.

2. Delete the default JMS host IMS host by using the delete-jms-host subcommand:

```
> asadmin delete-jms-host --target glassfish-cluster-name default_JMS_host
```

3. Create a JMS host for each broker in the broker cluster by using the create-jms-host subcommand.

For each broker, use an asadmin create-jms-host of the form:

```
> asadmin create-jms-host --target glassfish-cluster-name --mqhost broker-host
--mqport broker-port --mquser mq-user --mqpassword mq-user-password
jms-host-name-for-broker
```

- Start the brokers in the cluster by using the Message Queue improkerd command, as described in "Managing Broker Clusters" in Open Message Queue Administration Guide.
- 5. Create instances in the GlassFish Server cluster, as described in To Create an Instance Centrally and To Create an Instance Locally.

Connection Failover

The use of Message Queue broker clusters provides JMS connection failover, including several options that control how connection failures are handled.

Use the Administration Console's Java Message Service page to configure these options. To display this page, click the configuration for the GlassFish cluster or instance in the navigation pane, and then click the Java Message Service link on the Configuration page.

The way in which connection failover operates depends on whether the broker cluster is configured to be conventional or enhanced:

- In a conventional cluster, when a broker fails, clients may reconnect to any other broker in the cluster. The Reconnect field specifies whether reconnection should take place, and the Address List Behavior and Address List Iterations fields specify how the client chooses what broker to fail over to.
- In an enhanced cluster, when a broker fails, another broker automatically takes over its messages and clients. Clients automatically fail over to the appropriate broker. The Reconnect, Address List Behavior and Address List Iterations fields are ignored.

For more information on connection failover, including how failover on conventional clusters differs from failover on enhanced clusters, see "Automatic Reconnection" in Open Message Queue Administration Guide.

Reconnect

Applies only to conventional clusters. Enables reconnection and connection failover. When disabled, the Java Message Service does not attempt to reconnect if a connection fails.

Reconnect Interval

Specifies the number of seconds between reconnection attempts. If it is too short, this time interval does not give a broker time to recover. If it is too long, the wait time might represent an unacceptable delay. The default value is 5 seconds.

Reconnect Attempts

Specifies the number of attempts to connect (or reconnect) to a particular JMS host before trying another host in the JMS host list. The host list is also known as the Address List. Hosts are chosen from the address list either in order or randomly, depending on the setting of Address List Behavior.

Address List Behavior

For conventional clusters, this field specifies how the Java Message Service selects which JMS host in the JMS hosts list to initially connect to, and if the broker fails, how the Java Message Service selects which JMS host in the JMS hosts list to fail over to.

For enhanced clusters, this field specifies how the Java Message Service selects which JMS host in the JMS hosts list to initially connect to.

When performing initial connection or, for conventional clusters only, when performing failover, then if this attribute is set to Priority, the Java Message Service tries to connect to the first JMS host specified in the JMS hosts list and uses another one only if the first one is not available. If this attribute is set to Random, the Java Message Service selects the JMS host randomly from the JMS hosts list. If that host is not available, another one is chosen randomly.

The default for Embedded and Local JMS host types is Priority, and the default for the Remote JMS host type is Random.

For Embedded and Local JMS host types, the Java Message Service ensures that the Message Queue broker servicing a clustered instance appears first in that instance's IMS host list.

Thus, having Priority as the default Address List Behavior ensures that an application deployed to a clustered instance will always try to create its initial connection to that instance's co-located broker.

If there are many clients attempting a connection using the same connection factory, use the Random setting to prevent them from all attempting to create their initial connection to the same JMS host.

Address List Iterations

For conventional clusters, this field specifies the number of times the Java Message Service iterates through the JMS hosts list in an effort to establish its initial connection. If the broker fails, this field specifies the number of times the Java Message Service iterates through the JMS hosts list in an effort to fail over to another broker.

For enhanced clusters, this field specifies the number of times the Java Message Service iterates through the JMS hosts list in an effort to establish its initial connection. If the broker fails, this field is not used when performing reconnection.

You can override these settings using JMS connection factory settings. For details, see "Administering JMS Connection Factories and Destinations" in GlassFish Server Open Source Edition Administration Guide.

Load-Balanced Delivery to MDBs

When a message-driven bean (MDB) application is deployed to a GlassFish cluster, incoming messages are delivered randomly to MDBs without regard to the cluster instances in which they are running.

If the MDB is configured to receive messages from a durable or non-durable subscription on a topic, then only one MDB instance across the whole GlassFish cluster will receive each message.

For more information about these features, see "About Shared Topic Subscriptions for Clustered Containers" in *Open Message Queue Administration Guide*.

RMI-IIOP Load Balancing and Failover

This chapter describes using high-availability features for remote EJB references and INDI objects over RMI-IIOP in GlassFish Server.

- Overview
- InitialContext Load Balancing
- Per-Request Load Balancing (PRLB)

Overview

With RMI-IIOP load balancing, IIOP client requests are distributed to different server instances or name servers. The goal is to spread the load evenly across the cluster, thus providing scalability. IIOP load balancing combined with EJB clustering and availability also provides EJB failover.

The following topics are addressed here:

- General Requirements for Configuring Load Balancing
- **Load Balancing Models**

General Requirements for Configuring Load Balancing

Oracle GlassFish Server provides high availability of remote EJB references and NameService objects over RMI-IIOP, provided all the following apply:

- Your deployment has a cluster of at least two instances.
- Java EE applications are deployed to all instances and clusters that participate in load balancing.
- RMI-IIOP client applications are enabled for load balancing.

GlassFish Server supports load balancing for Java applications executing in the Application Client Container (ACC). See Enabling RMI-IIOP Hardware Load Balancing and Failover.

> **Note:** GlassFish Server does not support RMI-IIOP load balancing and failover over secure sockets layer (SSL).

Load Balancing Models

GlassFish Server supports two general models for load balancing:

InitialContext Load Balancing

When a client performs a JNDI lookup for an object, the Naming Service creates a InitialContext (IC) object associated with a particular server instance. From then on, all lookup requests made using that IC object are sent to the same server instance. InitialContext load balancing can be configured automatically across an entire cluster.

Per-Request Load Balancing (PRLB)

Per Request Load Balancing (PRLB) is a method for load balancing stateless EJBs that enables load-balancing for each request to an EJB instance. PRLB chooses the first node in a cluster to use on each request. PRLB is configured on a per-EJB basis.

InitialContext Load Balancing

The following topics are addressed here:

- InitialContext Summary
- InitialContext Algorithm
- Enabling RMI-IIOP Hardware Load Balancing and Failover

InitialContext Summary

When InitialContext load balancing is used, the client calls the InitialContext() method to create a new InitialContext (IC) object that is associated with a particular server instance. JNDI lookups are then performed on that IC object, and all lookup requests made using that IC object are sent to the same server instance. All EJBHome objects looked up with that InitialContext are hosted on the same target server. Any bean references obtained henceforth are also created on the same target host. This effectively provides load balancing, since all clients randomize the list of live target servers when creating InitialContext objects. If the target server instance goes down, the lookup or EJB method invocation will failover to another server instance. All objects derived from same InitialContext will failover to the same server instance.

IIOP load balancing and failover happens transparently. No special steps are needed during application deployment. IIOP load balancing and failover for the GlassFish Server supports dynamically reconfigured clusters. If the GlassFish Server instance on which the application client is deployed participates in a cluster, the GlassFish Server finds all currently active IIOP endpoints in the cluster automatically. Therefore, you are not required to manually update the list of endpoints if a new instance is added to the cluster or deleted from the cluster. However, a client should have at least two endpoints specified for bootstrapping purposes, in case one of the endpoints has failed.

InitialContext Algorithm

GlassFish Server uses a randomization and round-robin algorithm for RMI-IIOP load balancing and failover.

When an RMI-IIOP client first creates a new InitialContext object, the list of available GlassFish Server IIOP endpoints is randomized for that client. For that InitialContext object, the load balancer directs lookup requests and other InitialContext operations to an endpoint on the randomized list. If that endpoint is not available then a different random endpoint in the list is used.

Each time the client subsequently creates a new InitialContext object, the endpoint list is rotated so that a different IIOP endpoint is used for InitialContext operations. The rotation is randomized, so the rotation is not to the next endpoint in the list, but instead to a random endpoint in the list.

When you obtain or create beans from references obtained by an InitialContext object, those beans are created on the GlassFish Server instance serving the IIOP endpoint assigned to the InitialContext object. The references to those beans contain the IIOP endpoint addresses of all GlassFish Server instances in the cluster.

The *primary endpoint* is the bean endpoint corresponding to the InitialContext endpoint used to look up or create the bean. The other IIOP endpoints in the cluster are designated as *alternate endpoints*. If the bean's primary endpoint becomes unavailable, further requests on that bean fail over to one of the alternate endpoints.

You can configure RMI-IIOP load balancing and failover to work with applications running in the ACC.

Enabling RMI-IIOP Hardware Load Balancing and Failover

You can enable RMI-IIOP load balancing and failover for applications running in the application client container (ACC). Weighted round-robin load balancing is also supported.

To Enable RMI-IIOP Hardware Load Balancing for the Application Client Container

This procedure provides an overview of the steps necessary to enable RMI-IIOP load balancing and failover with the application client container (ACC). For additional information on the ACC, see "Developing Clients Using the ACC" in GlassFish Server *Open Source Edition Application Development Guide.*

Before You Begin

The first five steps in this procedure are only necessary if you are enabling RMI-IIOP load balancing on a system other than the DAS. This is common in production environment, but less common in a development environment. For example, a developer who wants to experiment with a cluster and load balancing might create two instances on the same system on which the DAS is running. In such cases, these steps are unnecessary.

- **1.** Go to the *install_dir* /bin directory.
- Run package-appclient.
 - This utility produces an appclient.jar file. For more information on package-appclient, see package-appclient(1M).
- **3.** Copy the appclient.jar file to the machine where you want your client and extract it.
- 4. Edit the asenv.conf or asenv.bat path variables to refer to the correct directory values on that machine.
 - The file is at *appclient-install-dir* /config/.
 - For a list of the path variables to update, see package-appclient(1M).
- **5.** If required, make the appclient script executable.
 - For example, on UNIX use chmod 700.
- Find the IIOP listener port number for at least two instances in the cluster.
 - You specify the IIOP listeners as endpoints in Add at least two target-server elements in the sun-acc.xml file..

For each instance, obtain the IIOP listener ports as follows:

a. Verify that the instances for which you want to determine the IIOP listener port numbers are running.

```
asadmin> list-instances
```

A list of instances and their status (running, not running) is displayed.

The instances for which you want to display the IIOP listener ports must be running.

b. For each instance, enter the following command to list the various port numbers used by the instance.

```
asadmin> get servers.server.instance-name.system-property.*.value
```

For example, for an instance name in1, you would enter the following command:

```
asadmin> get servers.server.in1.system-property.*.value
```

7. Add at least two target-server elements in the sun-acc.xml file.

Use the endpoints that you obtained in Find the IIOP listener port number for at least two instances in the cluster...

If the GlassFish Server instance on which the application client is deployed participates in a cluster, the ACC finds all currently active IIOP endpoints in the cluster automatically. However, a client should have at least two endpoints specified for bootstrapping purposes, in case one of the endpoints has failed.

The target-server element specifies one or more IIOP endpoints used for load balancing. The address attribute is an IPv4 address or host name, and the port attribute specifies the port number. See "client-container" in GlassFish Server Open Source Edition Application Deployment Guide.

As an alternative to using target-server elements, you can use the endpoints property as follows:

```
jvmarg value = "-Dcom.sun.appserv.iiop.endpoints=host1:port1,host2:port2,..."
```

- **8.** If you require weighted round-robin load balancing, perform the following steps:
 - **a.** Set the load-balancing weight of each server instance.

```
asadmin set instance-name.lb-weight=weight
```

b. In the sun-acc.xml, set the com.sun.appserv.iiop.loadbalancingpolicy property of the ACC to ic-based-weighted.

```
<client-container send-password="true">
 cproperty name="com.sun.appserv.iiop.loadbalancingpolicy" \
    value="ic-based-weighed"/>
```

9. Deploy your client application with the --retrieve option to get the client jar file. Keep the client jar file on the client machine.

For example:

```
asadmin --user admin --passwordfile pw.txt deploy --target cluster1 \
--retrieve my dir myapp.ear
```

10. Run the application client as follows:

```
appclient --client my_dir/myapp.jar
```

Example 11-1 Setting Load-Balancing Weights for RMI-IIOP Weighted Round-Robin Load Balancing

In this example, the load-balancing weights in a cluster of three instances are to be set as shown in the following table.

Instance Name	Load-Balancing Weight
i1	100
i2	200
i3	300

The sequence of commands to set these load balancing weights is as follows:

```
asadmin set i1.1b-weight=100
asadmin set i2.1b-weight=200
asadmin set i3.1b-weight=300
```

Next Steps

To test failover, stop one instance in the cluster and see that the application functions normally. You can also have breakpoints (or sleeps) in your client application.

To test load balancing, use multiple clients and see how the load gets distributed among all endpoints.

See Also

See Enabling the High Availability Session Persistence Service for instructions on enabling the session availability service for a cluster or for a Web, EJB, or JMS container running in a cluster.

Per-Request Load Balancing (PRLB)

The following topics are addressed here:

- **PRLB Summary**
- **Enabling Per-Request Load Balancing**

PRLB Summary

Per Request Load Balancing (PRLB) is a method for load balancing stateless EJBs that enables load-balancing for each request to an EJB instance. PRLB chooses the first node in a cluster to use on each request. By contrast, InitialContext (hardware) load balancing chooses the first node to use when the InitialContext is created, and each request thereafter uses the same node unless a failure occurred.

PRLB is enabled by means of the boolean per-request-load-balancing property in the glassfish-ejb-jar.xml deployment descriptor file for the EJB. If this property is not set, the original load balancing behavior is preserved.

Note: PRLB is only supported for stateless session beans. Using PRLB with any other bean types will result in a deployment error.

Enabling Per-Request Load Balancing

You can enable Per-Request Load Balancing (PRLB) by setting the boolean per-request-load-balancing property to true in the glassfish-ejb-jar.xml deployment descriptor file for the EJB. On the client side, the initContext.lookup method is used to access the stateless EJB.

To Enable RMI-IIOP Per-Request Load Balancing for a Stateless EJB

This procedure describes how to enable PRLB for a stateless EJB that is deployed to clustered GlassFish Server instances. This procedure also provides an client-side example for accessing a stateless EJB that uses PRLB.

Choose or assemble the EJB that you want to deploy.

In this example, an EJB named TheGreeter is used.

For instructions on developing and assembling an EJB for deployment to GlassFish Server, refer to the following documentation:

- "Using Enterprise JavaBeans Technology" in GlassFish Server Open Source Edition Application Development Guide
- "EJB Module Deployment Guidelines" in GlassFish Server Open Source Edition Application Deployment Guide
- "Assembling and Deploying an Application Client Module" in GlassFish Server Open Source Edition Application Deployment Guide
- Set the per-request-load-balancing property to true in the glassfish-ejb-jar.xml deployment descriptor file for the EJB.

For more information about the glassfish-ejb-jar.xml deployment descriptor file, refer to "The glassfish-ejb-jar.xml File" in GlassFish Server Open Source Edition Application Deployment Guide

For example, the glassfish-ejb-jar.xml file for a sample EJB named TheGreeter is listed below.

```
<glassfish-ejb-jar>
  <enterprise-beans>
    <unique-id>1</unique-id>
    <eib>
      <ejb-name>TheGreeter</ejb-name>
    <indi-name>greeter</indi-name>
    <per-request-load-balancing>true</per-request-load-balancing>
    </eib>
  </enterprise-beans>
</glassfish-ejb-jar>
```

3. Deploy the EJB.

If the EJB was previously deployed, it must be redployed.

For instructions on deploying EJBs, refer to the following documentation:

"To Deploy an Application or Module" in GlassFish Server Open Source Edition Application Deployment Guide

- "To Redeploy an Application or Module" in *GlassFish Server Open Source* Edition Application Deployment Guide
- Verify the PRLB configuration by looking for the following FINE message in the CORBA log file:

Setting per-request-load-balancing policyfor EJB EJB-name

5. Configure a client application to access the PRLB-enabled EJB.

For example:

```
public class EJBClient {
   public static void main(String args[]) {
   try {
   // only one lookup
   Object objref = initContext.lookup("test.cluster.loadbalancing.ejb.\
     TestSessionBeanRemote");
       myGreeterRemote = (TestSessionBeanRemote)PortableRemoteObject.narrow\
                                            TestSessionBeanRemote.class);
   } catch (Exception e) {
   }
    for (int i=0; i < 10; i++) {
    // method calls in a loop.
        String theMessage = myGreeterRemote.sayHello(Integer.toString(i));
        System.out.println("got"+": " + theMessage);
        }
   }
}
```

See Also

See Enabling the High Availability Session Persistence Service for instructions on enabling the session availability service for a cluster or for a Web, EJB, or JMS container running in a cluster.

Per-Request Load	Balancing	(PRLB)
------------------	-----------	--------